External Parameters for Numerical Weather Prediction and Climate Application EXTPAR v5_14 User and Implementation Guide

Hermann Asensio / Martina Messmer / Daniel Lüthi / Katie Osterried / Jonas Jucker / Jacopo Canton / Philipp Sommer / Jürgen Helmert

February 10, 2025

Contents

1		rall Description	5
	1.1		5
	1.2	Output external parameters	6
2	Soft	ware modules	10
_	2.1		10
	2.2		12
	2.3		12
	2.0	building	LZ
3	Fort	ran modules	14
	3.1	extpar_topo_to_buffer	14
			14
			20
	3.2		20
		3.2.1 Short description of the subprogram <i>extpar_landuse_to_buffer</i>	20
			25
		3.2.3 Used namelist files and data in-/output:	26
	3.3	extpar_aot_to_buffer	26
		3.3.1 Short description of the subprogram <i>extpar_aot_to_buffer</i>	26
		3.3.2 Used namelist files and data in-/output:	27
	3.4	extpar_soil_to_buffer	28
		3.4.1 Short description of the subprogram <i>extpar_soil_to_buffer</i>	28
		3.4.2 Used namelist files and data in-/output:	30
	3.5	1	31
		3.5.1 Short description of the subprogram <i>extpar_flake_to_buffer</i>	31
		$^{\prime}$. $^{\prime}$	31
	3.6		32
			32
		\cdot 1	32
	3.7		32
		3.7.1 Short description of the subprogram <i>extpar_consistency_check</i>	32
	D. Al	ann mar divida	
4			36
	4.1		36
	4.2		36
			36 37
	4.3	\cdot 1	37 37
	4.5		37 37
			38
	4.4	$^{\prime}$	38
	1.1	A CONTRACTOR OF THE CONTRACTOR	38
			38
	4.5	$^{\prime}$ 1	38
	1.0	*	38
			39
	4.6	$^{\prime}$ 1	39
	1.0		39
			39
	4.7	$^{\prime}$	39
	1.7	1	39
			4 0
	4.8	~ 1	4 0
		*	40

Contents

	4.9 4.10	4.8.2 Used namelist files and data in-/output: extpar_edgar_to_buffer 4.9.1 Short description of the subprogram extpar_edgar_to_buffer 4.9.2 Used namelist files and data in-/output: extpar_cdnc_to_buffer 4.10.1 Short description of the subprogram extpar_cdnc_to_buffer 4.10.2 Used namelist files and data in-/output:	40 40 40 41 41 41
5	Curr	rent limitations	41
	5.1	General limitations	41
6	Nam	nelist Input for Extpar	42
	6.1	Namelist files	42
	6.2	Grid definition	43
		6.2.1 general	43
		6.2.2 Icon	44
		6.2.3 COSMO	44
	6.3	Orography	44
	6.4	Land Use data	47
	6.5	Aerosol optical depth	48
	6.6	Climatological 2m temperature	48
	6.7	NDVI data	48
	6.8	EDGAR data	49
	6.9	CDNC data	49
		hwsdART data	49
		Soil data	49
		Freshwater Lake data	50
		Albedo data	50
		ISA data	51
		AHF data	51
		Emissivity parameter	51
		ERA parameter	51
	6.18	Consistency check	52

This short overview of the 'EXTPAR' software describes the working environment and the necessary steps to generate external parameters for numerical weather prediction and climate applications. More detailed information on specific modules of extpar can be found in the technical and scientific documentation.

1 Overall Description

Numerical Weather Prediction (NWP) models and Climate models require geographical localized datasets like the topographic height of the earth surface, the plant cover, the distribution of land and sea and, dependent on the schemes used, a variety of other external parameters.

The EXTPAR software system (EXTPAR - External Parameter for Numerical Weather Prediction and Climate Application) is able to generate external parameters for the different models COSMO and ICON. The software can run on a UNIX or Linux system where the raw data is stored. It allows operators (experienced users) running the scripts to create new external parameters controlled by user specifications like the model domain.

The following steps are performed for the generation of external parameters:

- 1. The target grid has to be specified. The supported target grids are
 - Rotated and non-rotated longitude-latitude grid (COSMO)
 - Icosahedral Triangular grids (ICON) with optionally higher resolution in selected regions ('local zooming')
- 2. The different raw data sets are aggregated to the target grid considering all raw data elements which are within the target grid element. If the target grid has a higher resolution than the input grid on which the raw data is available either an interpolation is performed or the target grid is filled with the nearest neighbor, but sub-grid scale statistical calculations (e.g. subgrid scale variance of orograhic height) are dismissed.
- 3. All the different external parameter sets have to be checked for consistency against each other. In case of conflicts default values are set automatically. In the NetCDF output, information on the input data and the processing software is given.

1.1 Input raw datasets

The information for the external parameters is aggregated from various raw datasets for land use data, orography or soil data, see table 1 for a detailed list of the raw datasets.

The input data for Extpar is stored in a git-LFS repository at https://gitlab.dkrz.de/extpar-data/extpar-input-data. Instructions for downloading the whole repository or updating with new datasets can be found in the git-LFS repository. For access to the input data repository, contact the current Extpar source code administrator.

Dataset	Source	Resolution
GLOBE orography	NOAA/NGDC	30"
ASTER orography	METI/NASA	1"
(limited domain: 60°N - 60°S)		
MERIT/REMA orography	Composite DEM	3" (90m)
Globcover 2009	ESA	10"
GLC2000 land use	JRC Ispra	30"
GLCC land use	USGS	30"
Ecoclimap-SG land use	CNRS and Meteo France	300m
ESA CCI-LC	ESA	10"
DSMW Digital Soil Map of the World	FAO	5'
HWSD Harmonized World Soil Database	FAO/IIASA/ISRIC/ISSCAS/JRC	30"
HWSD Harmonized World Soil Database	KIT	30"
USDA		
NDVI Climatology, SEAWiFS	NASA/GSFC	2.5'
CRU near surface climatology	CRU University of East Anglia	0.5 degree
Aerosol Optical thickness	NASA/GISS	4x5 degree
_	(Global Aerosol Climatology Project)	
AeroCom Global AOD data	AeroCom Project	1 degree
MACC-II climatological AOD (2003-2012)	ECMWF	1.125 degree
MACv2 monthly AOD, SSA and ASY data	MPI, RHM	1 degree
CAMS monthly 3D-climatology		
11 types of aerosols	ECMWF, RHM	3 degree
Global lake database (GLDB)	DWD/RSHU/MeteoFrance	30"
MODIS albedo	NASA	5′
MODIS derived soil albedo values	Community Land Model 3.5	30'
CAMEL Emissivity	NASA	5km
EDGAR Emissions	European Commission /JRC/PBL	0.1 degree
MODIS cloud droplet number climatol-	NASA	1 degree
ogy Q06		

Table 1: Input raw datasets

1.2 Output external parameters

The output fields with the external parameters are shown in table 2.

external parameter	short name	unit	raw dataset
geometrical height	HSURF	m	GLOBE/ASTER/
			MERIT/REMA
geopotential of earth surface	FIS	m^2s^{-1}	GLOBE/ASTER/
			MERIT/REMA
standard deviation of subgrid scale oro-	SSO_STDH	m	GLOBE/ASTER/
graphic height			
			MERIT/REMA
anisotropy of topography	SSO_GAMMA	1	GLOBE/ASTER/
			MERIT/REMA
angle between principal axis of orography	SSO_THETA	1	GLOBE/ASTER/
and global E			
			MERIT/REMA
mean slope of subgrid scale orography	SSO_SIGMA	1	GLOBE/ASTER/
			MERIT/REMA
surface roughness	Z0	m	GLC2000,
			GLOBE/ASTER/

external parameter	short name	unit	raw dataset
			MERIT/REMA
Slope aspect	SLOPE_ASP	deg	GLOBE/ASTER/
			MERIT/REMA
Slope angle	SLOPE_ANG	deg	GLOBE/ASTER/
			MERIT/REMA
Horizon angles (resolution from 15deg)	HORIZON	deg	GLOBE/ASTER/
			MERIT/REMA
Skyview factor	SKYVIEW	-	GLOBE/ASTER/
•			MERIT/REMA
soil texture	SOILTYP	-	DSMW/HWSD
fraction of sand	FR_SAND	%	HWSD
fraction of silt	FR_SILT	%	HWSD
fraction of clay	FR_CLAY	%	HWSD
fraction of organic carbon	FR_OC	%	HWSD
bulk density	BULK_DENS	gcm^{-3}	HWSD
deep soil texture	SUBSOILTYP	-	HWSD
deep soil fraction of sand	SUB_FR_SAND	%	HWSD
deep soil fraction of silt	SUB_FR_SILT	%	HWSD
deep soil fraction of clay	SUB_FR_CLAY	%	HWSD
deep soil fraction of organic carbon	SUB_FR_OC	%	HWSD
deep soil bulk density	SUB_BULK_DENS	gcm^{-3}	HWSD
Fraction of Heavy Clay	fr_hcla	1 1	HWSD_USDA
Fraction of Fleavy Clay Fraction of Silty Clay	fr_silc	1	HWSD_USDA
	fr_lcla	1	HWSD_USDA
Fraction of Light Clay	fr_icia fr_sicl		I I
Fraction of Silty Clay Loam		1	HWSD_USDA
Fraction of Clay Loam	fr_cloa	1	HWSD_USDA
Fraction of Silt	fr_silt	1	HWSD_USDA
Fraction of Silty Loam	fr_silo	1	HWSD_USDA
Fraction of Sandy Clay	fr_scla	1	HWSD_USDA
Fraction of Loam	fr_loam	1	HWSD_USDA
Fraction of Sandy Clay Loam	fr_sclo	1	HWSD_USDA
Fraction of Sandy Loam	fr_sloa	1	HWSD_USDA
Fraction of Loamy Sand	fr_lsan	1	HWSD_USDA
Fraction of Sand	fr_sand	1	HWSD_USDA
Fraction of Undefined or Water	fr_udef	1	HWSD_USDA
ground fraction covered by plants max	PLCOV_MX	1	GLC2000/Globcover/
(vegetation period)			ESA CCI-LC
ground fraction covered by plants min	PLCOV_MN	1	GLC2000/Globcover/
(vegetation period)			ESA CCI-LC
ground fraction covered by artificial (ur-	URBAN	1	GLC2000/Globcover/
ban) areas			ESA CCI-LC
ground fraction covered by artificial (ur-	URBAN	1	GLC2000/Globcover/ES
ban) areas			CCI-LC/ LCZs with
			TERRA_URB
ground fraction covered by deciduous for-	FOR_D	1	GLC2000/Globcover/
est			ESA CCI-LC
skin conductivity	SKC	$Wm^{-1}K^{-1}$	Globcover/ESA CCI-
•			LC
root depth	ROOTDP	m	GLC2000/Globcover/
•			ESA CCI-LC
leaf area index max(vegetation period)	LAI_MX	1	GLC2000/Globcover/ES.
, O 1			CCI-LC

1 Overall Description

external parameter	short name	unit	raw dataset
leaf area index min (vegetation period)	LAI_MN	1	GLC2000/Globcover/ ESA CCI-LC
plant resistance	PRS_MIN	sm^{-1}	GLC2000/Globcover/ ESA CCI-LC
long wave surface emissivity	EMISS_RAD	1	GLC2000/Globcover/ ESA CCI-LC
(monthly) normalized differential vegetation index	NDVI	1	SEAWIFS
Annual maximum of normalized differential vegetation index	NDVI_MAX	1	SEAWIFS
(monthly) proportion of actual value/ maximum normalized			
differential vegetation index	NDVI_RATIO	1	SEAWIFS
(monthly) optical thickness from black carbon aerosol	AER_BC	1	GACP
(monthly) optical thickness from dust aerosol	AER_DUST	1	GACP
(monthly) optical thickness from organic aerosol	AER_ORG	1	GACP
(monthly) optical thickness from SO4 aerosol	AER_SO4	1	GACP
(monthly) optical thickness from sea salt aerosol	AER_SS	1	GACP
(monthly) aerosol optical thickness for RG92 spectral bands	AOT12	1	MACv2
(monthly) single scattering albedo for RG92 spectral bands	SSA12	1	MACv2
(monthly) asymmetry factor for RG92 spectral bands	ASY12	1	MACv2
(monthly) layer-integrated mass of Sea Salt with			
dry radius in the range 0.03-0.5 microns (monthly) layer-integrated mass of Sea	Sea_Salt_bin1	kgm^{-2}	CAMS
Salt with dry radius in the range 0.5-5.0 microns	Sea_Salt_bin2	kgm^{-2}	CAMS
(monthly) layer-integrated mass of Sea Salt with	oca-oart_om2	ngm	Critivio
dry radius in the range 5.0-20.0 microns (monthly) layer-integrated mass of Min-	Sea_Salt_bin3	kgm^{-2}	CAMS
eral Dust with dry radius in the range 0.03-0.55 microns	Mineral_Dust_bin1	kgm^{-2}	CAMS
(monthly) layer-integrated mass of Mineral Dust with	Willierar_Dust_Diff1	куш	CAIVIS
dry radius in the range 0.55-0.9 microns	Mineral_Dust_bin2	kgm^{-2}	CAMS
(monthly) layer-integrated mass of Mineral Dust with			
dry radius in the range 0.9-20.0 microns (monthly) layer-integrated mass of hy-	Mineral_Dust_bin3	kgm^{-2}	CAMS
drophilic Organic Matter	Organic_Matter_hydr	rokolorili c 2	CAMS
(monthly) layer-integrated mass of hydrophobic	Organic Iviation Injur	ордине	CHIVIO
Organic Matter	Organic_Matter_hyd	rophobic	CAMS

external parameter	short name	unit	raw dataset	
(monthly) layer-integrated mass of hy-				
drophilic				
Black Carbon	Black_Carbon_hydro	philia ⁻²	CAMS	
(monthly) layer-integrated mass of hy-				
drophobic	DI 1 C 1 1 1		C 1 2 10	
Black Carbon	Black_Carbon_hydro	pkgbic ²	CAMS	
(monthly) layer-integrated mass of Sul-	Sulfates	kgm^{-2}	CAMS	
fates	1 101		G.1.7.60	
(monthly) Pressure at base of layer	half_level_pressure	Pa	CAMS	
Near surface temperature (climatological	T_2M_CL	K	CRU	
mean)	DEDELLIA		CLDD	
Lake Depth	DEPTH_LK	m	GLDB	
Lake Fraction	FR_LAKE	1	GLDB	
(monthly) albedo	ALB_DIF12	%	MODIS	
(monthly) Near Infrared Albedo	ALNID	%	MODIS	
(monthly) Ultra Violet Albedo	ALUVD	%	MODIS	
soil albedo for dry soils	ALB_DRY	%		and
			Model 3.5	
soil albedo for saturated soils	ALB_SAT	%		and
			Model 3.5	
fraction of impervious surface area	ISA	1	NOAA, EEA or LO	$\mathbb{C}Zs$
			with TERRA_URB	
anthropogenic heat flux	AHF	Wm^{-2}	NOAA or LCZs w	vith
			TERRA_URB	
subgrid-scale slope parameter	S_ORO	1	GLOBE, ASTER,	
			MERIT/REMA	
EMISS yearly maximum for climatology	EMISS_MAX	1	CAMEL	
1998-2003	T) (700		C.L. CTT	
monthly mean EMISS climatology 1998-	EMISS	1	CAMEL	
2003	EN MOC NO ATT	1	CANCEL	
(monthly) proportion of actual value/-	EMISS_MRAT	1	CAMEL	
maximum normalized differential vegeta-				
tion index	ED DAVED	1	1.07-	-1:11-
Urban paved fraction	FR_PAVED	1		vith
IIIdaa hadidha faratira	URB_BLDFR	1	TERRA_URB	-1.1.
Urban building fraction	UKD_DLDFK	1		vith
The an level dies of height	TIDD DI DII		TERRA_URB	-: 41-
Urban building height	URB_BLDH	m		vith
The an arrange baids to saidth watio	URB_H2W	1	TERRA_URB	-: 41-
Urban canyon height-to-width ratio	UKD_FIZVV	1		vith
Urban shortwave albedo	URB_SALB	1	TERRA_URB	-: 41-
Urban Shortwave albedo	UKB_SALB	1	I .	vith
Tide or the owner letter de	TIDD TAID	1	TERRA_URB	-1:11-
Urban thermal albedo	URB_TALB	1		vith
The an aminoisity	LIDD EMIC	1	TERRA_URB	-: 41-
Urban emissivity	URB_EMIS	1		vith
Tirban haat canductivity	URB_HCON	1	TERRA_URB LCZs w	vith
Urban heat conductivity	UND_FICUN	1		ıιn
Linhan haat canasity	I IDD LICAD	1/1/	TERRA_URB	-;+L
Urban heat capacity	URB_HCAP	J/K	LCZs w TERRA_URB	vith
Annual black carbon emissions	omi ho	$kg m^{-2} s^{-1}$	EDGAR	
	emi_bc	$\frac{kg m^{-2} s^{-1}}{kg m^{-2} s^{-1}}$		
Annual organic carbon emissions	emi_oc	$\kappa g m - s$	EDGAR	

external parameter	short name	unit	raw dataset
Annual sulfur dioxide carbon emissions	emi_so2	$kg m^{-2} s^{-1}$	EDGAR
Annual ammonia emissions	emi_nh3	$kg m^{-2} s^{-1}$	EDGAR
Annual nitrogen oxides emissions	emi_nox	$kg m^{-2} s^{-1}$	EDGAR
Monthly cloud droplet number climatol-	cdnc	cm^{-3}	MODIS
ogy			

Table 2: Output external parameters

2 Software modules

2.1 Overview

The software EXTPAR is composed of thirteen autonomous programmes. Twelve programmes are responsible for aggregating a raw data to the target grid, which is specified by the user. The thirteenth program, the consistency check, is performed in the end. The executables are called extpar_*_to_buffer, whereas the star stands for ahf (anthropogenic heat flux), aot (aerosol optical thickness), cru (temperature climatology of the Climate Research Unit (CRU)), landuse, topo, ndvi (normalized difference vegetation index), soil, flake (fraction lake), isa (impervious surface area), albedo, emiss (emissivity) and era (ERA climatologies) respectively. In Fig. 1 a schematic representation of EXTPAR is drawn. For the sake of clarity only the topography and land-use path is shown. The same can be applied for the other ten raw data sets. For all these programs there exist namelists. Most of the namelists only contain the name and path of the raw data file and the name of the buffer file, which is later used for the consistency check, and the name of the output of the final external variables.

The software modules read from the following namelist files:

- INPUT_AOT
- INPUT_LU
- INPUT_ORO, INPUT_OROSMOOTH, INPUT_RADTOPO, INPUT_SCALE_SEP
- INPUT_SOIL
- INPUT_hwsdART
- INPUT_FLAKE
- INPUT_grid_org
- INPUT_COSMO_GRID or INPUT_ICON_GRID
- namelist.py

The namelists 'INPUT_grid_org' and either 'INPUT_COSMO_GRID' or 'INPUT_ICON_GRID' are used in all the programs, as they contain the general information of the target grid to which the raw data should be aggregated. The namelist file 'namelist.py' is read by all Python programmes.




Figure 1: Schematic illustration of the software EXTPAR.

2.2 Hybrid Python-CDO structure

For three of the external parameters calculated by EXTPAR, namely albedo, NDVI, and the Hadley CRU climatologies, problems appeared with target resolutions much higher than the provided input data set resolutions. The problem is that not all target grid points get assigned a proper value when using the legacy Fortan code and interpolation method.

The algorithm used in the legacy Fortran modules aggregates source grid point values onto the target grid where the input data is finer than the target grid and uses bi-linear interpolation to fill the remaining grid points where the input data is sparser than the target grid. However, starting from a 5 km global resolution for the target grid, points can potentially get assigned unreasonable values because of the insufficiency of the bi-linear interpolation algorithm.

To resolve this issue, for Extpar Version 5.4 a rewrite of those Fortran modules in Python, using the more sophisticated interpolation methods from CDO with support for all grids was conducted. Because the interpolation methods implemented in CDO are faster then those in Fortran for large model grids, <code>emiss_to_buffer</code> is written in Python as well. A rewrite in Python only makes sense for Fortran modules that do simple calculations with the data. These calculations can easily be substituted with CDO-commands in the Python modules. For modules doing complex calculations and providing many namelist parameters the user can define, like <code>extpar_topo_to_buffer</code> or <code>extpar_landuse_to_buffer</code>, a rewrite in Python is not planned.

The interpolation algorithms selected are:

- albedo distance-weighted average remapping
- NDVI first order conservative remapping
- EDGAR first order conservative remapping
- CDNC first order conservative remapping
- CRU climatology distance-weighted average remapping
- emissivity first order conservative remapping
- **ERA climatology** first order conservative remapping
- AHF/ISA bilinear interpolation

The description of the used algorithms can be found via the CDO documentation: (https://code.mpimet.mpg.de/projects/cdo/embedded/cdo.pdf).

2.3 Summary

The external parameters can be generated by using thirteen programs to aggregate the various raw datasets to the target grid and after this by calling the final program for the important consistency check.

- 1. In a first step, the target grid and other parameters have to be specified by the user in the runscript (see section 6.2 for the details).
- 2. Then the aggregation of the raw datasets listed in table 1 to the given target grid can be performed by calling following executables
 - extpar_aot_to_buffer
 - extpar_cru_to_buffer
 - extpar_landuse_to_buffer
 - extpar_topo_to_buffer
 - extpar_ndvi_to_buffer

- extpar_soil_to_buffer
- extpar_flake_to_buffer
- extpar_alb_to_buffer
- extpar_isa_to_buffer
- extpar_ahf_to_buffer
- extpar_emiss_to_buffer
- extpar_hwsdART_to_buffer
- extpar_era_to_buffer
- extpar_edgar_to_buffer

These programs generate intermediate NetCDF files ("buffer") with the aggregated data.

3. The executable

extpar_consistency_check

reads in the buffer-files, performs an automated consistency check, and finally generates the output fields listed in table 2.

The task of the consistency check that is performed at the end is to find inconsistencies in the soil data, the lake data and the NDVI data. In the soil data problems may appear between the soil type and the land-use, in particular for water and ice grid elements. For the fraction lake, minimal and maximal lake depth must be introduced and some seas such as the Caspian and the Dead Sea as well as Lake Constance must be defined manually. For more information see chapter 3.7.

3 Fortran modules

3.1 extpar_topo_to_buffer

3.1.1 Short description of the subprogram extpar_topo_to_buffer

The program *extpar_topo_to_buffer* aggregates the orography of the GLOBE, ASTER, or MERIT/REMA dataset to the target grid.

Target grid definition

The first part of this program contains several routines that read the namelists defined in the run script (see chapter 6 for more information on the run scripts). The first routine (init_target_grid) collects all the information needed to define the target grid with an integrated routine that gathers the variables given in the namelist 'INPUT_grid_org'. The variable igrid_type, which can either be 1 ('ICON') or 2 ('COSMO'), is an integer switch to define the target grid.

Then a routine reads the namelist of the corresponding grid, which is either 'INPUT_ICON_GRID' or 'INPUT_COSMO_GRID', depending on the chosen grid type. The run script contains only one of the two namelists. This must be manually changed by the user. These namelists contain among other variables the resolution of the grid, the user specified domain and the location of the center of the grid (for closer information about the namelists compare chapters 6.2.2 - 6.2.3). This allows an exact definition of the target grid.

Subgrid-scale slope

The namelist INPUT_ORO contains the parameter lcompute_sgsl, to determine whether SGSL should be calculated from the respective raw topography data. Formerly this was done in a separate executable extpar_sgsl_to_buffer.exe. From Release 5.3 onwards, the SGSL calculation was incorporated into the execututable 'extpar_topo_to_buffer. As an intermediate step, the SGSL is written out to NetCDF, one separate file for each raw topography tile is required. In case the preprocessed SGSL NetCDF are already available, setting the parameter lpreproc oro= .false., deactivates the preprocessing, but not the aggregation of SGSL to the target grid. We recommend to only do the preprocessing for the GLOBE dataset, because the computational cost for the ASTER or MERIT/REMA dataset is very high and no validation has taken place for this dataset.

Topographic correction for radiation

In a second step, the namelist 'INPUT_RADTOPO' is read. It contains the information if the user desires the calculation of the topographical corrected radiation parameters or not. If the switch is set to .TRUE. a border is added to the COSMO domain, as the computations need grid points beyond the edges of the normal domain. For ICON an on the fly extension of the grid is not possible, leading to missing data at the boundaries. Therefore the namelist-switch <code>max_missing</code> defines the treshold for the allowed fraction of missingness. Altough the topographical corrected radiation can be calculated for both ICON and COSMO grids, the two sets of fields cannot be considered as identical, because for ICON grids one assumes plain (non-tilted) grid-cells, whereas for COSMO one also takes into account self-shading and effects related to tilted-plains for the skyview-factor.

The number of horizons is specified in the namelist. For the COSMO-7 and COSMO-2 setup 24 horizons are recommended. The icon-only parameter *radius* defines the radial distance taken into account for the topographical corrected radiation parameters. To account for the anisotropic behaviour of longwave-radiation, the namelist parameter *itype_scaling* defines the power of the term *SIN(horizon-angle)* in the equation of the skyview-factor. Due to performance reasons, for ICON the parameter *min_circ_cov* determines how many grid-cells can be skipped on the circumference considered for the computations.

Raw topography data The namelist 'INPUT_ORO' gives the possibility to switch between two raw orographical data sets (GLOBE, ASTER, or MERIT/REMA). In contrast to the 90m-data of MER-IT/REMA, it must be considered, that the 30m-data of ASTER are not completely downloaded and are therefore not globally available. The downloaded region extends from 60°N to 60°S and from 180°W to 180°E. It is not recommended to derive the topographical parameters from ASTER if the region is beyond 60 degrees north or south. The ASTER files are arranged as displayed in Fig. 2. As the computational time of the program extpar_topo_to_buffer depends mainly on the number of ASTER files that are read in, two new parameters are introduced in the namelist. These two parameters give the number of columns and rows of the used ASTER files. The filenames of the desired ASTER files must be given manually. Figure 2 gives an example on how to use these parameters in the case of COSMO-2. A similar approach is used for MERIT/REMA DEM as shown in Figure 3. The latitude range between 60-90 deg S is covered by REMA DEM, which was mapped to the MERIT data format by BKG, Germany. If GLOBE is used the columns and rows are set to 4 and all GLOBE files must be listed in the topo_files parameter. A check in the program extpar_topo_to_buffer is introduced, which gives a warning if the borders of the domain are exceeded. This is followed by an abortion of this program. As there is no need to calculate the subgrid scale parameters (SSO) for high resolution setups, there is the logical switch *lsso_parm* to turn off the calculation of the SSOs.

\80°	° W 150			W 60°			E 30		° E 90		0° E 150	°E 1	80° E 160° N
v –	T001	T002	T003	T004	T005		T007	T008	T009	T010	T011	T012	54° N
,	T013	T014	T015	T016	T017	T018	T019	T020	T021	T022	T023	T024	48° N
, -	T025	T026	T027	T028	T029	T030	T031	T032	T033	T034	T035	T036	42° N
	T037	T038	T039	T040	T041	T042	3 то43	T044	T045	T046	T047	T048	36° N
	T049	T050	T051	T052	T053	T054	T055	T056	T057	T058	T059	T060	30° N
	T061	T062	T063	T064	T065	T066	T067	T068	T069	T070	T071	T072	24° N
	T073	T074	T075	T076	T077	T078	T079	T080	T081	T082	T083	T084	18° N
	T085	T086	T087	T088	T089	T090	T091	T092	T093	T094	T095	T096	12° N
	T097	T098	T099	T100	T101	T102	T103	T104	T105	T106	T107	T108	6° N
	T109	T110	T111	T112	T113	T114	T115	T116	T117	T118	T119	T120	0° N
	T121	T122	T123	T124	T125	T126	T127	T128	T129	T130	T131	T132	6° S
5	T133	T134	T135	T136	T137	T138	T139	T140	T141	T142	T143	T144	12° S
, -	T145	T146	T147	T148	T149	T150	T151	T152	T153	T154	T155	T156	12°S
, _	T157	T158	T159	T160	T161	T162	T163	T164	T165	T166	T167	T168	24° S
5	T169	T170	T171	T172	T173	T174	T175	T176	T177	T178	T179	T180	30° S
5	T181	T182	T183	T184	T185	T186	T187	T188	T189	T190	T191	T192	36° S
	T193	T194	T195	T196	T197	T198	T199	T200	T201	T202	T203	T204	42° S
<u>`</u>	T205	T206	T207	T208	T209	T210	T211	T212	T213	T214	T215	T216	42 S 48° S
	T217	T218	T219	T220	T221	T222	T223	T224	T225	T226	T227	T228	54° S
	T229	T230	T231	T232	T233	T234	T235	T236	T237	T238	T239	T240	
0° S 180° W 150° W 120° W 90° W 60° W 30° W 0° E 30° E 60° E 90° E 120° E 150° E 180°													

Figure 2: Illustration of the single domains of the 240 ASTER tiles. An example of how the three parameters ntiles_columns, ntiles_row and topo_files in the namelist could look like is given in red.

Furthermore the variables of the namelist 'INPUT_ORO', which cover all the raw topographical data information, are fed into the program. In this namelist the path of the raw data is given as well as the names of the topography data files. An integer switch allows the choice between the highly resolved, non-global topography ASTER, the global but coarser MERIT/REMA and the coarser and

global data set GLOBE (1: GLOBE, 2: ASTER, 3: MERIT/REMA). Furthermore the logical switch to decide whether the SSO parameters are desired or not is read. In order to define the right number of raw data tiles the variables ntiles_column and ntiles_row must be available in the namelist. Additionally, the names for the buffer and output files are defined.


The topography data files must be manually changed in the run script, when switching from GLOBE to ASTER, or MERIT/REMA and vice versa.

Then, the number of tiles of the raw topography data is defined (this varies between the raw data sets: 16 tiles for GLOBE, 1 - 240 tiles for ASTER, 72 tiles for MERIT/REMA). This value is the product of the number of tiles in each column and each row. The variables concerning the raw topography are allocated and in a further step filled with the according values. These values are the edges of each raw topography tile, the number of gridpoints in x- and y-direction, as well as the resolution in both directions. These are directly deduced from the raw data NetCDF files. Finally the borders of the ASTER domain are defined, when ASTER is used.

After the definition of the target grid and the topography set, a check examines the compatibility of the user specified input with the target grid; as ASTER is not globally available at the moment it is checked that the user specified domain is contained in the current ASTER domain. And, if this is not the case, the <code>extpar_topo_to_buffer</code> is aborted with an error message.

Scale separation input

The namelist 'INPUT_SCALE_SEP' gives all the information needed to calculate the SSO parameters and roughness length based on a 3 km filtered topography. Thus the logical switch lscale_separation must be read to decide if a scale separation is desired or not. Furthermore the raw data files and path must be provided. Note that the lscale_separation can only be set to .TRUE. if GLOBE is used as topography, as there is no ASTER or MERIT/REMA based 3 km filtered topography available yet.



Additionally the user must decide if the computation of the SSO parameters make sense or not. Table 3 can give some assistance to come to the right decision.

Resolution	Calculation of standard deviation	lscale_separation
Model resolution is smaller	SSOs: $\sigma = 0$.FALSE.
than raw data resolution	z0: $\sigma = 0$	
Model resolution is greater	SSOs: $\sigma = 0$.FALSE.
than the raw data resolution	z0: $\sigma = \sum (model - raw data)^2$	and
but smaller than 3 km		lsso_param = .FALSE.
Model resolution is greater	SSOs: $\sigma = \sum (model - 3km \ filt)^2$.TRUE.
than 3 km	z0: $\sigma = \sum (3km \ filt - raw \ data)^2$	

Table 3: Recommendations on the usage of the scale separation. Be aware that the actual model topography resolution is approximately twice as large as the model resolution. E.g. COSMO-2: The resolution of the topography is approximately 4 km.

Orographical smoothing input

The last namelist that must be read before allocating the orography is the namelist 'INPUT_ORO-SMOOTH', which defines all the variables needed to perform an orographical smoothing. The lfilter_oro logical switch, controls the computation of the smoothing in EXTPAR.

Aggregation of the raw topography to the target grid

The subroutine <code>det_topo_tiles_grid</code> defines the grid of each raw topography data tile. For this, the start and end latitude and longitude of each tile, the distance between two grid points in the latitudinal and longitudinal direction (dlat, dlon) as well as the number of grid points in both directions (nlat, nlon) are derived for each tile. Additionally, the grid for the whole GLOBE, ASTER, or MERIT/REMA domain is derived; This is done in the subroutine <code>det_topo_grid</code>.

Before the raw topography can be aggregated on the target grid, the target variables must be allocated. These variables include the land fraction (FR_LAND), the elevation of the surface (hh_target), the standard deviation of the elevation (stdh_topo), the roughness length of the topography (z0_topo), the sub-grid scale orography parameters (theta_topo, aniso_topo and slope_topo) and the topographical corrected radiation parameters (slope_asp, slope_ang, horizon and skyview). For the ICON grid some additional parameters must also be allocated.

The following paragraphs describe computations on the raw data grid.

The subroutine <code>agg_topo_data_to_target_grid</code> does the actual work of aggregating the raw topography to the target grid. The whole topographical data set is divided in bands of 500 grid points in the latitudinal direction and the whole range of the raw data domain in the longitudinal direction (compare for this the black band in Fig. 4). This band is introduced to optimize memory usage, as it is not possible to read the whole raw data in one pass. In order to read the correct raw data the start and end index of each tile (green crosses in Fig. 4) is defined. These indices are additionally associated with a start and end index (red circles in Fig. 4) inside the band. The definition of the two kinds of indices is performed by the routine <code>get_topo_tile_block_indices</code>. With this band the whole raw data is read step by step as suggested in Fig. 4. If the scale separation is desired the same procedure is applied to the 3 km filtered topography.

After this step, a temporary variable of elevation values is filled. This variable consists of three rows, which comprises the whole longitude range of the raw topography data. This is used to deduce the gradients of the topography, which are calculated as averaged differences between one eastern and one western grid point (x-gradient) or with one northern and one southern grid point (y-gradient). From these gradients in x- and y- direction also the squared gradients and the dx*dy are computed.




Figure 4: Schematic illustration of the filling of the raw data with a 500 grid points long band. The green crosses indicate the start end end latitudes and longitudes of each raw topography tile (light blue tiles), whereas the red circles show the indices inside the band, where the green indices of the tiles must be placed.

This is followed by a call of the subroutine <code>find_rotated_lonlat_grid_element_index</code>. This routine defines to which grid element of the target grid a certain grid element of the raw topography belongs. The allocation of the raw data points to the target grid element is performed as shown in Fig. 5 a). All raw data elements that are closer than half a grid point (green box) to the target point (red circle) are used to define the value at the corresponding target grid point. Only the green grid elements in Fig. 5 b) belong to a target grid element. The rest of the raw topography is unused.

The elevations of raw data pixels that belong to one target grid element are summed up, and the number of raw data pixels contributing to one target grid element is tracked. A summation of the raw data values for each target grid element is also performed for the squared elevation, which is later used for the standard deviation, and for the gradients calculated before, which are required for the computation of the subgrid scale orography parameters. The latter is only calculated if the SSO parameters are desired. When making use of the scale separation the squared differences between the original and the 3 km filtered topography must be computed at every grid point. This is needed in order to calculate the roughness length specific standard deviation. After these calculations, the temporary rows are shifted to the north and the computation is repeated for the next center line. As soon as a band of 500 rows is finished a new one will be read in.


Now that all auxiliary variables are available, all loops over the raw topography data are closed and a new one over all the grid points of the target grid is opened.

The following paragraphs describe computations on the target grid.

First of all the elevation is calculated as the mean of all the raw topography data points that are enclosed in one target grid point.

As soon as the topography is available on the target grid, the orographical smoothing is applied using the subroutine *do_orosmooth*.

In a next step the variance and the standard deviation of the elevation at each target grid point is estimated. Subsequently, the SSO parameters angle of principle axis, anisotropy factor and slope parameter are calculated according to Lott and Miller (1996). These SSOs are only calculated if the SSO






Figure 5: a) Illustration of the aggregation of the raw data to the target grid. The red circle indicates a target grid point, while the green rectangle represents the part of the raw data that is aggregated on the target grid point. b) Showing the target grid on top of the raw data set, where only the green grid points of the raw data are used for the target grid.

switch is set to .TRUE. and if the standard deviation of the height is more than 10 meters, as the trivial case of the ocean is tried to be avoided. If the scale separation is switched on the SSOs are based on the 3 km filtered topography. Finally the orographical roughness length is calculated using the standard deviation, but only if at least one raw data pixel is present in the target grid element.

In the case where no raw topography data pixel is available in a target grid, a weighted bilinear interpolation between neighboring raw data grid element is performed to obtain an elevation in all target grid points. This mainly happens if the raw topography has a similar resolution as the target grid. If the bilinear interpolation needs to be applied, all the SSO as well as z0 are set to zero for this grid element. With this step the end of the subroutine <code>agg_topo_data_to_target_grid</code> is reached.

In the program <code>extpar_topo_to_buffer</code> an additional check on SSOs and z0 is performed. If none of the elements of the target grid is associated with at least ten raw data pixels, or as soon as one single element is not associated with any raw data pixel, all the SSOs and z0 are set to zero.

As soon as there is a value for all the target grid elements, the calculation for the topographical corrected radiation parameters can start, if desired at all.

Finally NetCDF files for the orography based external parameters are created, where different NetCDF

routines are used for each grid type, as different parameters are needed for each of them. If the lradtopo is set to .TRUE. the enlarged domain is cut back to the user specified domain, before writing it to the NetCDF file.

3.1.2 Used namelist files and data in-/output:

- namelist files: INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID, INPUT_ORO, INPUT_OROSMOOTH, INPUT_RADTOPO
- data input (GLOBE): GLOBE_A10.nc GLOBE_P10.nc
- data input (ASTER): ASTER_T001.nc ASTER_T240.nc
- data input (MERIT/REMA): MERIT_N90-N60_E150-E180.nc4 REMA_BKG_S60-S90_W180-W150.nc4
- data input (filtered): GLOBE_A_filt_lanczos_window.nc GLOBE_P_filt_lanczos_window.nc, GLOBE_A_filt_tukey_0.75_3.0_it4.nc - GLOBE_P_filt_tukey_0.75_3.0_it4.nc
- Output: buffer file with orography data (/orography_io_extpar/ orography_buffer_file) output file with orography data (used in extpar_cru_to_buffer) (/orography_io_extpar/ orography_output_file)

3.2 extpar_landuse_to_buffer

3.2.1 Short description of the subprogram extpar_landuse_to_buffer

The executable *extpar_landuse_to_buffer* aggregates the land use data to the target grid. Five different raw datasets can be processed: Globcover, GLC2000, GLCC, ESA CCI-LC and Ecoclimap Second Generation (Ecoclimap-SG from here onwards). As GLC2000 and Globcover do not include Antarctica, GLCC or ESA CCI-LC data can be used for the missing areas. The landuse executable also includes the TERRA-URB module, controlled by the logical switch *l_terra_urb*; see section 3.2.2 for details.

Target grid definition

The definition of the target grid is done by reading the namelist 'INPUT_grid_org'. This namelist contains the information about the grid type, which can either be ICON or COSMO. With the information about the grid type, the namelist containing the grid definition can be read. The name of the namelist must be changed manually by the user, according to the chosen grid type. The namelist must either be 'INPUT_ICON' or 'INPUT_COSMO'. For a more exact description of the target grid definition, read the subsection 'Target grid definition' in section 3.1. After specifying the grid definition the southern band of the target grid is defined. This information is important, as the two raw data sets GLC2000 and Globcover do not cover the region below 60 degrees south. If this region is desired by the user, the third data set must be considered for the domain below the southern band. Additionally the target fields for the land use data are allocated.

Raw landuse data

In a next step the namelist 'INPUT_LU' is read. It contains an integer switch (*i_landuse_data*) that gives the possibility to choose between the five different raw data sets e.g., 1 (Globcover), 2 (GLC2000), 3 (GLCC), 5 (ESA CCI-LC), and 6 (Ecoclimap-SG). For Globcover one can additionally choose to use the corine landuse dataset by setting the logical switch (*l_use_corine*) to TRUE. Furthermore the path and the filename of the desired raw data and of GLCC are specified there. The user must adjust the filename and path manually according to the chosen raw data in *i_landuse_data*. In addition the name of the desired lookup table is read, which again can be chosen by the user using an integer switch *ilookup_table_lu*. The lookup tables are described in more detail in table 5. The names of the buffer files for the target landuse fields and for the target GLCC fields are also specified in this namelist. Finally, the aforementioned *l_terra_urb* logical switch can be specified (the default value is .FALSE.).

After having read the namelists, the number of tiles of the raw data set is defined. The number of tiles is set to 1 as default and must only be changed for the raw data set Globcover or ESA CCI-LC, which are composed of 6 tiles. The basic information of the Globcover tiles, such as the latitude and longitude edges and the resolution is allocated according to the number of tiles. Later these variables are filled with the respective information, read from the NetCDF files directly.

For the remaining procedures the three different raw land use data have their separate routines, which are constructed identically.

The allocation of the data is done using the number of grid points in the latitudinal and longitudinal direction. Furthermore the land-use target fields are allocated using the target grid for the dimension size and the number of land-use classes. The land-use classes differ for the three raw data sets and are described in more detail in table 4.

Data Set (Total number of Classes)	Number of Class	Name of Class
GLOBCOVER (23)		
	01	irrigated croplands
	02	rainfed croplands
	03	mosaic cropland (50-70%) - vegetation (20-50%)
	04	mosaic vegetation (50-70%) - cropland (20-50%)
	05	closed broadleaved evergreen forest
	06	closed broadleaved deciduous forest
	07	open broadleaved deciduous forest
	08	closed needleleaved evergreen forest
	09	open needleleaved decid. or evergr. forest
	10	mixed broadleaved and needleleaved forest
	11	mosaic shrubland (50-70%) - grassland (20-50%)
	12	mosaic grassland (50-70%) - shrubland (20-50%)
	13	closed to open shrubland
	14	closed to open herbaceous vegetation
	15	sparse vegetation
	16	closed to open forest regulary flooded
	17	closed forest or shrubland permanently flooded
	18	closed to open grassland regularly flooded
	19	artificial surfaces
	20	bare areas
	21	water bodies
	22	permanent snow and ice
	23	undefined
Corine (23)		
Corine (23)		
(CLC: 2.1.2, 2.1.3)	11	irrigated croplands
(CLC: 2.1.1)	14	rainfed croplands
(CLC: 2.4.2, 2.4.3)	20	'mosaic cropland (50-70%) - vegetation (20-50%)
(CLC: 2.4.4)	30	mosaic vegetation (50-70%) - cropland (20-50%)
	40	closed broadleaved evergreen forest
(CLC: 3.1.1)	50	closed broadleaved deciduous forest
	60	open broadleaved deciduous forest
(CLC: 3.1.2)	70	closed needleleaved evergreen forest
(CLC: 1.4.1)	90	open needleleaved decid. or evergr. forest
(CLC: 3.1.3)	100	mixed broadleaved and needleleaved forest
(CLC: 2.2.3, 3.2.4)	110	mosaic shrubland (50-70%) - grassland (20-50%)
(CLC: 2.2.2, 3.2.2)	120	mosaic grassland (50-70%) - shrubland (20-50%)
(CLC: 2.2.1)	130	closed to open shrubland
(CLC: 2.3.1, 3.2.3)	140	closed to open herbaceous vegetation

Data Set	Number of Class	Name of Class
(Total number of Classes)	4.50	
(CLC: 3.2.1)	150	sparse vegetation
(67.6.44.5)	160	closed to open forest regulary flooded
(CLC: 4.1.2)	170	closed forest or shrubland permanently flooded
(CLC: 4.1.1)	180	closed to open grassland regularly flooded
(CLC: 1.1.1, 1.1.2, 1.2.1,	190	artificial surfaces
1.2.2, 1.2.3, 1.2.4, 1.3.3,		
1.4.2)		
(CLC: 3.3.1, 3.3.2, 3.3.3,	200	bare areas
3.3.4, 1.3.1, 1.3.2)		
(CLC: 4.2.1, 4.2.2, 4.2.3,	210	water bodies
5.1.1, 5.1.2, 5.2.1, 5.2.2,		
5.2.3)		
(CLC: 3.3.5)	220	permanent snow and ice
(CLC: 9.9.9)	230	undefined
GLC2000 (23)		
	01	evergreen broadleaf tree
	02	deciduous broadleaf tree closed
	03	deciduous broadleaf tree open
	04	evergreen needleleaf tree
	05	deciduous needleleaf tree
	06	mixed leaf tree
	07	fresh water flooded tree
	08	saline water flooded tree
	09	mosaic tree / other natural vegetation
	10	burnt tree cover
	11	
	12	evergreen shrubs closed-open
	13	deciduous shrubs closed-open
		herbaceous cover closed-open
	14	sparse herbaceous or grass
	15	flooded shrub or herbaceous
	16	cultivated and managed areas
	17	mosaic crop/tree/natural vegetation
	18	mosaic crop/shrub or grass
	19	bare areas
	20	water bodies
	21	snow and ice
	22	artificial surfaces
	23	undefined
GLCC (24)		
	01	urban and built-up land
	02	dryland cropland and pasture
	03	irrigated cropland and pasture
	04	mixed dryland/irrigated
	05	cropland/grassland mosaic
	06	cropland/woodland mosaic
	07	grassland
	08	shrubland
	09	mixed shrubland/grassland
	10	savanna
	11	decidous broadleaf forest
	12	decidous needleleaf forest
	13	evergreen broadleaf forest
	14	evergreen needleleaf forest
		0

Data Set (Total number of Classes)	Number of Class	Name of Class
	15	mixed forest
	16	water bodies
	17	herbaceous wetland
	18	wooded wetland
	19	barren or sparsely vegetated
	20	herbaceous tundra
	21	wooded tundra
	22	mixed tundra
	23	bare ground tundra
	24	snow or ice
Ecoclimap-SG (33)		
	01	sea and oceans
	02	lakes
	03	rivers
	04	bare land
	05	bare rock
	06	permanent snow
	07	boreal broadleaf deciduous
	08	temperate broadleaf deciduous
	09	tropical broadleaf deciduous
	10	temperate broadleaf evergreen
	11	tropical broadleaf evergreen
	12	boreal needleleaf evergreen
	13	temperate needleleaf evergreen
	14	boreal needleleaf deciduous
	15	shrubs
	16	boreal grassland
	17	temperate grassland
	18	tropical grassland
	19	winter C3 crops (lower T & greater water avail.)
	20	summer C3 crops
	21	C4 crops (warmer environments)
	22	flooded trees
	23	flooded grassland
	24	LCZ1: compact high-rise
	25	LCZ2: compact midrise
	26	LCZ3: compact low-rise
	27	LCZ4: open high-rise
	28	LCZ5: open midrise
	29	LCZ6: open low-rise
	30	LCZ7: lightweight low-rise
	31	LCZ8: large low-rise
	32	LCZ9: sparsely built
	33	LCZ10: heavy industry

Table 4: Land-use classes for the different raw data sets. The Corine LandCover (CLC) classes in the left column indicate how the CLC is mapped to the corresponding GlobCover class.

After the allocation of the data a check is performed to query, if the user desires a domain that goes beyond the southern bound of the raw data. If it is the case, the GLCC target fields are allocated as well.

In case that Globcover is used, the grid for the single tiles must be defined as well.

Aggregation of the raw land-use data to the target field.

The definition and allocation part is done and the most important part, the aggregation of the raw data to the target grid can be performed. In order to be able to aggregate the data, the lookup table must first be initialized. The initial values differ for the various settings listed in table 5. Also the name of the lookup table must be defined using the integer numbers specified in the namelist 'INPUT_LU'. The integer number are listed together with their associated lookup table names in table 5.

Raw Data	Integer	Setting	Name of the lookup table
GLOBCOVER	1	operational settings	Asensio, 2011
	2	experimental settings, analog to lookup	Asensio, 2010
		tables of ECOCLIMAP	
GLC2000	1	operational settings of GME	Ritter, 2007
	2	operational settings of COSMO	Heise, 2005
	3	experimental settings, analog to lookup	Asensio, 2010
		tables of ECOCLIMAP	
GLCC	1	operational settings of GME	Ritter, 2007
	2	operational settings of COSMO	Heise, 2005
	3	experimental settings, analog to lookup	Asensio, 2010
		tables of ECOCLIMAP	
ESA CCI-LC	1	experimental settings	Helmert, 2019
Ecoclimap-SG	1	Globcover analogue with added LCZs	-
-		from Oke	

Table 5: Names of the lookup tables and the different possible settings for each raw land-use data set.

The following paragraphs describe computations on the raw data grid.

For GLC2000 and GLCC, the raw data is read in lines of a complete longitude going from 180 degrees east to 180 degrees west, through a loop over the latitude. Before any calculation is performed, it is tested if the value of the latitude is contained inside the targed domain. In case it is not, the loop is cycled. Reading of the data line-wise can be done from the NetCDF file directly.

Using the routine *find_nearest_target_grid_element* each raw data pixel is assigned to a target grid point. A more precise description and a figure that describes the procedure can be found in paragraph 'Aggregation of the raw topography to the target grid' and in Fig. 5 in section 3.1.

As Globcover and ESA CCI-LC are composed of six tiles, the reading of the raw data must be performed in a different way than for the other three data sets. The reading of the data for Globcover is done in the same way as for the topography. Compare the paragraph 'Aggregation of the raw topography to the target grid' in section 3.1. (As there is no need to calculate gradients for the land use, the corresponding variable, which contains three lines of raw data, is not used.

The lookup table is then fed with the land use class, which gives a value for all the target fields listed in table 6.

Variable long name	Variable short name	Remark
Fraction Land	FR_LAND	_
Ice fraction	FR_ICE	
Plant cover maximum	PLCOV_MX	
Plant cover minimum	PLCOV_MN	
Leaf area index maximum	LAI_MX	
Leaf area index minimum	LAI_MN	
Minimal stomata resistance	RS_MIN	
Urban area fraction	URBAN	
Fraction of deciduous forest	FOR ₋ D	
Fraction of evergreen forest	FOR_E	

Variable long name	Variable short name	Remark
Longwave surface emissivity	EMISS_RAD	
Root depth	ROOTDP	
Roughness length	Z0	

Table 6: The variables that are computed using the raw land-use data.

The number of grid points that fall into the same target grid and land use class are summed up. The values of the target fields are weighted with the whole pixel area and summed up. Except for the emissivity, which is the only land-use parameter that also has valid values over water, only land pixels are considered. Values that depend on the plant cover, such as PLCOV_MX, PLCOV_MN, LAI_MN, LAI_MX, RS_MIN, FOR_E, FOR_D, ROOTDP and z0, are weighted with the plant cover maximum in addition to the pixel area.

The following paragraphs describe computations on the target grid.

The total area and the land area of each target grid point is first defined. Then the weighted sums of the target fields derived in the previous step are normalized to obtain the definite values. The emissivity and the number of land use classes are normalized by the total area to obtain the correct emissivity and area fraction of each land use class. The other parameters are only considered if the area_land is larger than zero: FR_LAND and FR_ICE are normalized with the total area, URBAN, FOR_D, FOR_E, PLCOV_MN and PLCOV_MX are normalized by the land area, the ROOTDP, LAI_MN, LAI_MX and RS_MIN are normalized by the area covered by plants. If only sea pixels are found, all the fields are undefined.

Finally land-use classes are defined for target grid points that do not contain any raw data pixel. In contrary to the topography, where a bilinear interpolation is performed, here the nearest neighbor is searched. The associated land use class is used with the lookup tables, and the target fields are defined.

The target fields are written to a NetCDF buffer file, which can later be used for the consistency check. There is a file for the chosen land use data set, and one, if needed at all, for the GLCC land use data. Finally the allocated memory is deallocated again.

3.2.2 TERRA-URB

NOTE: *currently the TERRA-URB module in extpar only works with the Ecoclimap-SG database*, as this is the only database available for extpar with an LCZ map.

The executable <code>extpar_landuse_to_buffer</code> also includes the TERRA-URB module, controlled by the logical switch <code>l_terra_urb</code>. This module uses a 2D map of local climate zones (LCZ) to determine a set of urban canopy variables used by TERRA-URB in COSMO/ICON, see table 7. The module aggregates the variables and outputs them to the <code>lu_buffer_file</code>. The aggregation procedure follows that of the other land use variables described in the previous sections. The TERRA-URB related variables then pass through the subprogram <code>extpar_consistency_check</code> (see section 3.7) and are written out to the final extpar file for both COSMO and ICON. ICON would typically ignore these fiels and just use the information from the <code>LU_CLASS_FRACION</code> field, as is done for other land use variables, except for when <code>ntiles=1</code> in which case it needs the 2D fields. The ISA and AHF extpar modules must be turned off when running with <code>l_terra_urb=.true</code>, as these fields are computed within the TERRA-URB module. The code for this module is based upon Matthias Demuzere's <code>WUDAPT-to-COSMO</code> [3] and Handrik Wouters' <code>SURY</code> [4] codes. The LCZ look-up tables are based on the values published in [1, 2].

Variable name	Description
FR_URBAN	Urban area fraction
ISA	Imprevious surface area
AHF	Anthropogenic heat flux
FR_PAVED	Fraction of impervious surface area
URB_FR_BLD	Urban building fraction

URB_H_BLD	Urban building height
URB_H2W	Urban canyon height to width ratio
URB_ALB_SO	Urban shortwave (solar) albedo
URB_ALB_TH	Urban thermal albedo
URB_EMIS	Urban emissivity
URB_HCON	Urban mean heat conductivity
URB_HCAP	Urban mean heat capacity

Table 7: Varialbes provided by the TERRA-URB module

3.2.3 Used namelist files and data in-/output:

- namelists files: INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID, INPUT_LU
- data input: GLC2000_byte.nc, GLCC_usgs_class_byte.nc, CORINE_globcover.nc, GLOBCOVER_0_16bit.nc - GLOBCOVER_5_16bit.nc, ECCI_300m_0.nc - ECCI_300m_5.nc, ECOCLIMAP_SG.nc
- Output: buffer file with landuse data (/lu_io_extpar/ lu_buffer_file) and buffer file with GLCC data (/glcc_io_extpar/ glcc_buffer_file)

3.3 extpar_aot_to_buffer

3.3.1 Short description of the subprogram extpar_aot_to_buffer

The executable *extpar_aot_to_buffer* aggregates aerosol optical thickness data to the target grid.

Target grid definition

The definition of the target grid is again done using the namelist 'INPUT_grid_org'. As the subroutines are exactly the same as the ones used in *extpar_topo_to_buffer*, it is referred to the subsection 'Target grid definition' in section 3.1, where the procedure is explained in more detail.

Raw aerosol optical depth data

The namelist 'INPUT_AOT' is kept very simple. It contains only the path and the name of the raw aerosol optical depth data. The integer switch (<code>iaot_type</code>) informs extpar which of the 4 available datasets has been chosen: 1 (Tegen), 2 (AeroCom), 3 (MACC-II), 4 (MACv2) or 5 (CAMS) . Additionally, also the filenames of the buffer and output files for the aggregated data is specified.

In order to allocate the variables used to read the raw data, the dimensions of the raw data is defined. These dimensions include the number of rows and columns of the NetCDF raw data file, the number of months, which is equal to 12, as a full yearly cycle is described, and the number of types of aerosols contained in the raw data file. This number is 5 for iaot_type=1,2 or 3, as the raw data file contains the aerosol optical thickness information of black carbon, dust, organic matter, sulfate and sea salt. iaot_type=4 is used for a new formulation of the radiation-aerosol interaction available only in version of COSMO later than 5.04. This provides data of the aerosol optical thickness, the single scattering albedo and the asymmetry factor for the 8 spectral bands defined in the RG92 radiation scheme. iaot_type=5 is used only for ICON model. The raw data file contains the layer-integrated mass information of 11 types of aerosols: Sea Salt (3 bin), Mineral Dust (3 bin), hydrophilic and hydrophobic organic matter, hydrophilic and hydrophobic black carbon and sulfate. Also the raw data file contains the pressure for 60 vertical levels. The 3 first data-sets which provide raw data for different aerosol

Raw	data set	resolution
Tege	en	4 x 5 degree
Aero	oCom	1 x 1 degree
MA	CC-II	1.125 x 1.125 degree
MA	Cv2	1 x 1 degree
CAN	ЛS	3 x 3 degree x 60 levels

Table 8: resolution of raw data-sets for aerosol optical depths.

types refer to Tegen¹, AeroCom² and MACC-II³ whereas the fourth data-set is derived from MACv2⁴ and the fifth data-set is derived from CAMS⁵.

In a next step, the complete raw data is read into memory; this is possible since the aerosol optical depth raw data is of rather coarse resolution (see table 8). Also, the grid of the raw data is determined from NetCDF meta data. Before the aggregation to the target grid can start, the target grid fields must be allocated, using the target grid, the number of months and aerosol types or spectral bands.

Aggregation of the aerosol optical depth to the target field

As the resolution of all raw data sets is so coarse, there is no need to go through the whole raw data set and find the corresponding target grid element. Here there is only one loop over the target grid. For every target grid element four surrounding raw data points are searched for. With these four points, a weight for the bilinear interpolation is computed. As the raw data grids of the 5 different aerosols are equal, the four surrounding points are the same for all months and aerosol types. Four new arrays (SW, SE, NE, NW) are then defined, which contain the four neighbor values, for each month and each type. These can now be used, together with the previously calculated weights, to calculate the bilinear interpolation.

Finally the data is saved in a NetCDF buffer and an output file, and the allocated variables are deallocated.

3.3.2 Used namelist files and data in-/output:

- namelists files: INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID, INPUT_AOT
- data input: aot_GACP.nc, aod_AeroCom1.nc, aod_MACC_2003-2012.nc, aod_MACC_2003-2012_proc.nc, aot_MACv2.nc, aot_CAMS_2003-2013.nc
- Output: buffer file with aerosol data (/aerosol_io_extpar/ aot_buffer_file)

¹Tegen, I., P. Hollrigl, M. Chin, I. Fung, D. Jacob, and J. Penner 1997. Contribution of different aerosol species to the global aerosol extinction optical thickness: Estimates from model results. J. Geophys. Res., 102, 23895-23915. http://pubs.giss.nasa.gov/abstracts/1997/Tegen_etal.html

²Kinne, S., M. Schulz, C. Textor, S. Guibert, Y. Balkanski, S.E. Bauer, T. Berntsen, T.F. Berglen, O. Boucher, M. Chin, W. Collins, F. Dentener, T. Diehl, R. Easter, J. Feichter, D. Fillmore, S. Ghan, P. Ginoux, S. Gong, A. Grini, J. Hendricks, M. Herzog, L. Horowitz, I. Isaksen, T. Iversen, A. Kirkevåg, S. Kloster, D. Koch, J.E. Kristjansson, M. Krol, A. Lauer, J.F. Lamarque, G. Lesins, X. Liu, U. Lohmann, V. Montanaro, G. Myhre, J. Penner, G. Pitari, S. Reddy, Ø. Seland, P. Stier, T. Takemura, and X. Tie: An AeroCom initial assessment optical properties in aerosol component modules of global models, Atmos. Chem. Phys., 6, 1815-1834, 2006. http://aerocom.met.no/aerocomhome.html

³Morcrette, J.-J., O. Boucher, L. Jones, D. Salmond, P. Bechtold, A. Beljaars, A. Benedetti, A. Bonet, J. W. Kaiser, M. Razinger, M. Schulz, S. Serrar, A. J. Simmons, M. Sofiev, M. Suttie, A. M. Tompkins, and A. Untch, 2009: Aerosol analysis and forecast in the ECMWF Integrated Forecast System. Part I: Forward modelling, J. Geophys. Res., 114D, D06206,doi:10.1029/2008JD011235 http://www.gmes-atmosphere.eu/

⁴Kinne, S., D. O'Donnel, P. Stier, S. Kloster, K. Zhang, H. Schmidt, S. Rast, M. Giorgetta, T. F. Eck, and B. Stevens (2013), MAC-v1: A new global aerosol climatology for climate studies, J. Adv. Model. Earth Syst., 5, 704–740, doi:10.1002/jame.20035.

⁵Bozzo, A., Benedetti, A., Flemming, J., Kipling, Z., Rémy, S. (2020). An aerosol climatology for global models based on the tropospheric aerosol scheme in the Integrated Forecasting System of ECMWF. Geoscientific Model Development, 13(3), 1007-1034.

3.4 extpar_soil_to_buffer

3.4.1 Short description of the subprogram extpar_soil_to_buffer

The executable *extpar_soil_to_buffer* aggregates soil data of the FAO Digital Soil Map of the World or of the Harmonized World Soil Data (HWSD) to the target grid.

Target grid definition

The definition of the target grid is again done using the namelist 'INPUT_grid_org'. As the subroutines are exactly the same as the ones used in *extpar_topo_to_buffer*, it is referred to the subsection 'Target grid definition' in section 3.1, where the procedure is explained in more detail.

Raw soil data

The variables for the raw soil data are read from the namelist 'INPUT_SOIL'. These variables are the path and the names of the raw data files and two switches to decide whether the FAO or the HWSD data should be used and if the deep soil data is desired or not. The integer switch *isoil_data* determines the raw data and processing used: 1 for FAO, 2 for the HWSD data-set⁶ and 3 for the use of HWSD data with mapping to TERRA soil types. The switch to choose the production of deep soil information is a logical (only applicable to isoil_data=2). Additionally, the names of the buffer files are specified. Be aware that a change of the integer switch from FAO to HWSD requires also the manual replacement of the raw data file names in the namelist.

After reading the namelist, a check is made on the production of subsoil characteristics. This is only supported for HWSD data, and a warning is issued in case of bad usage.

The dimensions of the raw soil data are defined, which include the number of grid points in the latitudinal and longitudinal direction, as well as the number of soil data code of the raw data. These values are needed to allocate the soil data with the proper size.

The mapping between raw data sets specific codes and some standard soil types is defined; this concerns the soil types 'undefined', 'default', 'ice' and 'water'.

As the soil data is provided in one single file, all data can be read in one shot. The data that are read from the NetCDF file are the texture and the slope of the soil data and the soil code. The aggregation of the data is done in a different way for the FAO and HWSD data, as these result in two completely different variables. Moreover, for HWSD data, to conserve memory, the topsoil data are allocated first and aggregated to the target grid, before the same is done for the subsoil.

Aggregation of the FAO and HWSD data with TERRA mapping to the target grid

The following paragraphs describe computations on the raw data grid.

The soil data is read using a loop over the latitude and the longitude. This results in a point-wise reading of the raw data. As soon as the point is read, its corresponding target grid element is defined. If the regular latitude/longitude grid point is not contained in the target grid, a new point is read. If however the point is inside the target grid, the aggregation can begin.

The number of raw data pixels is increased by one, if a raw data point can be assigned to a target grid point. This number is later used to define the fraction land defined by the soil data. The corresponding soil unit is deduced from the raw data. If the soil unit is zero, this is an ocean pixel and the number of sea points is increased by one. If the soil code differs from zero, the number of land points is increased by one. The soil code is then associated to either a special or a normal soiltype. For all the special soiltypes such as ice, rock, salt, histosols, dunes and no data flags the respective texture

⁶Release 5.0 of COSMO and 2.0 of INT2LM do not support HWSD data, as the representation of the soil associated with this new data set has changed and is based on the use of pedotransfer functions and on fraction of soil components (e.g. clay, silt, ...)

(coarse, medium, fine) are defined using a lookup table. All other soil units are described using the texture available in the raw data. These values define the final texture variable 'texture'.

The following paragraphs describe computations on the target grid.

In the following a loop is opened over the target grid points. First of all the fraction land is defined using the number of land pixels minus the number of inland water pixels, which is then averaged by the number of raw data pixels that were available for the target grid element. In a next step the texture for every target grid element is defined. For the special soiltypes (texture larger than 900) the corresponding number is associated. For the normal soiltypes (texture smaller than 900) the texture is calculated as average of the summed up texture. The resulting texture value is multiplied by 100 and converted into an integer number. This number is used to associate the final soiltype to every target grid element. The soiltypes are described in more detail in table 9. For target grid points that do not contain any raw data points, the nearest neighbor in the raw data is defined. If the target grid point is outside the raw data grid the slope is defined as zero and the texture as undefined.

TERRA Code	Soiltype	raw data code
1	ice and glacier ⁷	9001
2	rock, lithosols	9002
3	sand	9003 (salt), 9005 (shifting sands and dunes) and
		coarse texture
4	sandy loam	coarse to medium texture
5	loam (default soiltype)	9009 (undefined), 9012 (dominant part undefined),
		medium texture
6	loamy clay	medium to fine texture
7	clay	fine texture
8	histosols (peat)	9004
9	water	9000 (undefined: inland water), -9 (undefined:
		ocean)

Table 9: TERRA soiltypes and their respective FAO raw data codes.

Aggregation of the HWSD data to the target grid

The aggregation starts again with a loop over the latitudes and longitudes. For each grid point a target grid element is looked for. If there is a target grid element, the aggregation can start. The soiltype is defined using the raw data value, if it is above zero, and zero otherwise. Additionally, all the ocean, land and lake points are counted in order to determine the land fraction which is calculated as the difference between the summed up land and lake points normalized by the number of raw data pixels available. For target grid points with no raw data, the nearest neighbor in the raw data is defined.

The resulting soiltype is not yet usable, as it contains numbers coded in a world code and not in TERRA soiltypes. This transformation is done in the consistency check, where the special soiltypes of the HWSD data, specified in table 10, are packed in the variable 'SOILTYP' the normal soiltypes are given in fractions of sand, silt, clay and organic carbon, and the bulk density is also given.

TERRA Code	Soiltype	TERRA Code	Soiltype
1	ice and glacier	8	histosols (peat)
2	rock, lithosols	9	water
3	sand	10	alkali flat
4	sandy loam	11	shifting sand, dunes
5	loam (default soiltype)	12	Urban, human disturbed
6	loamy clay	225	Unknown
7	clay		

Table 10: New TERRA soiltypes deduced from the HWSD data.

Output of the soil data

The soiltypes and the fraction land, together with the undefined value, the latitudes and longitudes are saved in a NetCDF buffer file. This is later used to perform the consistency check, which is especially important for the HWSD data, as the main transformation of the data takes place there.

3.4.2 Used namelist files and data in-/output:

- namelists files: INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID, INPUT_SOIL
- data input: FAO_DSMW_double.nc, FAO_DSMW_float.nc, HWSD0_30_topsoil.nc, HWSD30_100_subsoil.nc

⁷Soiltypes written in bold indicate a special soiltype.

- Lookup tables for HWSD: LU_TAB_HWSD_UF.data, HWSD_DATA_COSMO.data, HWSD_DATA_COSMO_S.data
- Output: buffer file with soil data (/soil_io_extpar/ soil_buffer_file)

3.5 extpar_flake_to_buffer

3.5.1 Short description of the subprogram extpar_flake_to_buffer

The executable extpar_flake_to_buffer aggregates lake depth data and lake fraction to the target grid.

Target grid definition

The definition of the target grid is again done using the namelist 'INPUT_grid_org'. As the subroutines are exactly the same as the ones used in *extpar_topo_to_buffer*, it is referred to the subsection 'Target grid definition' in section 3.1, where the procedure is explained in more detail.

Raw lake data

As only the target grid dimensions are needed to allocate the target fields, this is done right after the definition of the target grid. Then the namelist 'INPUT_FLAKE' is read to define the path and the filename of the raw lake data. Also the names of the buffer and the output file for the consistency check are given. Once more the dimensions of the raw data are needed to allocate the raw data correctly; these dimensions are deduced from the netcdf file directly and the raw data grid is defined.

Aggregation of the lake data to the target grid

The following paragraphs describe computations on the raw data grid.

The data is read row-wise, through a loop over the latitudes, shipping all latitudes not inside the user specified domain. If a row is kept, a new loop over the longitudes is started to treat the raw data point-wise. For each point, the corresponding target field element is defined. This is done in the same way described in the subsection 'Aggregation of the topography to the target grid' in section 3.1 and Fig. 5. The number of raw data pixels that contribute to the target grid value are summed up as well as the lake depth, which is multiplied by a scale factor deduced from the area of each pixel that contributes to a lake fraction.

The following paragraphs describe computations on the raw data grid.

The lake fraction is derived and the lake depth is obtained by normalizing the weighted sum previously computed. Where no lake depth is available the value is set to undefined (-1). In case that no raw data pixel is available the nearest neighbor in the raw data is searched for.

The target fields are then written to a netcdf buffer and output file. Finally the allocated memory can be released.

3.5.2 Used namelist files and data in-/output:

- namelists files: INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID, INPUT_FLAKE
- data input: GLDB_lakedepth.nc
- Output: buffer file with flake data (/flake_io_extpar/ flake_buffer_file)

3.6 extpar_hwsdART_to_buffer

3.6.1 Short description of the subprogram extpar_hwsdART_to_buffer

This program processes HWSD (Harmonized World Soil Database) data and aggregates it onto a target grid.

The code is a module named "mo_agg_hwsdART" that contains a subroutine called "agg_hwsdART_data_to_target_g This subroutine is used to aggregate data from the HWSD dataset to a target grid. The HWSD dataset contains soil unit information classified according to the USDA soil classification system.

The module uses several other modules, including "mo_logging" for logging purposes, "mo_kind" to define kind parameters, "mo_hwsdART_data" to define the different soil types according to the USDA classification, "mo_hwsdART_tg_fields" to define variables related to the target grid, and "mo_grid_structures" to define grid structures.

The subroutine takes input parameters including the target grid structure ("tg"), the HWSDART soil unit data ("hwsdART_soil_unit"), the grid of HWSDART data ("hwsdART_grid"), and the longitude and latitude coordinates of the HWSDART grid ("lon_hwsdART" and "lat_hwsdART").

The subroutine initializes local variables and arrays to store the counts of different soil types in each grid element of the target grid. It also sets an undefined integer value and initializes the count of raw data pixels to zero.

The subroutine then iterates over the HWSDART grid and finds the nearest target grid element for each raw data pixel using the "find_nearest_target_grid_element" function. If the raw data pixel is out of the range of the target domain, it is skipped.

For each valid raw data pixel, the subroutine counts the number of raw data pixels in the target grid element and increments the count for the corresponding soil type in the local arrays.

After the iteration over the HWSDART grid, the subroutine iterates over the target grid to calculate the fraction of each soil type in each grid element. It divides the count of each soil type by the total number of raw data pixels in the grid element and stores the fractions in the corresponding variables.

The code aggregates the HWSD soil data in USDA scheme to a target grid, calculating the fraction of each soil type in each grid element for application in ICON-ART simulations.

3.6.2 Used namelist files and data in-/output:

- namelists files: INPUT_grid_org, INPUT_ICON_GRID, INPUT_hwsdART
- data input: HWSD0_USDA.nc
- Output: buffer file with fraction of soil type classes (hwsdART_extpar_ICON.nc)

3.7 extpar_consistency_check

3.7.1 Short description of the subprogram extpar_consistency_check

The *extpar_consistency_check* is performed after all raw data have been aggregated to the target grid to remove any inconsistencies that may appear among the different data and to derive additional information using multiple raw data sources.

Reading of namelists

Before the grid is defined, the namelists 'INPUT_RADTOPO', 'INPUT_ORO' and 'INPUT_SOIL' are read to obtain the settings of the different switches that are used (e.g. lradtopo, itopo_type, lsso_param, isoil_data, ldeep_soil). Then the namelist 'INPUT_grid_org' is read to obtain the target grid information and the grid type.

In a next step the 'INPUT_LU' is read by <code>extpar_consistency_check</code> to check if the GLCC data set is required, which is the case if the target grid domain reaches more to the south than the chosen raw land-use data set. (Globcover and GLC_2000 are not global.)

If the namelist INPUT_ERA is present (indicating that one uses the ERA climatologies generated by extpar_era_to_buffer) the buffer file name is retrieved. If this namelist is not present (legacy climatologies from ICON-REMAP-TOOL are used), the buffer file names in INPUT_CHECK are read. After that step, all other namelists of the Extpar modules are read in order to retrieve the buffer file name for each data set. These files are read and all the variables needed for the final external parameters file are allocated.

An additional namelist that is used is 'INPUT_CHECK', it contains a couple of switches to define the processing in the consistency check.

The first task after reading the namelists is to derive the correct land sea mask from the land use data. If the GLCC data must be used, the land sea mask below the southern band is deduced from GLCC.

Then the total roughness length is computed as the sum of the roughness length deduced from the land-use and the topography.

Consistency check for water and ice pixels

The definition of a water grid element is based on the land-use data. The vegetation is set to zero for all water grid elements and FAO derived soil type is set to water. For non water pixels with undefined or invalid soil type, the FAO derived soil type is either set to default, which is loam, or to ice for regions that are below 60 degrees south (where only Antarctica is located).

All the points that are classified as ice in the land-use data but not in the FAO derived soil type, are changed to ice in the latter; the vegetation of these pixels is set to zero.

The HWSD derived soiltype needs a transformation from the world code to the TERRA code, which is performed here. The world code is decoded with the TERRA HWSD lookup table, to define the regions that contain a special soiltype (see the special soiltypes in table 10). For each grid point the world code is associated to the single fractions of the soil composition, using an other lookup table. If there is a point that does not contain a bulk density it is calculated using the formula of the cultivated topsoil or the compact subsoil from Hollisa et al. (2012)⁸ and Woesten et al. (1999)⁹. Furthermore there is a special treatment of peat with histosols. The whole procedure is also done for the subsoil, if it is desired at all.

Consistency check of lake data

Water grid points are either declared as lake or ocean, thus over land a fraction lake and over the ocean a fraction ocean is defined. Where the fraction land deduced from the topography is smaller than 0.99 the fraction ocean is defined. All the other points are used to determine the fraction lake. Both fractions are defined such that fr_lake or fr_ocean plus fr_land_lu (fraction land deduced from land-use) sum up to one. Some smaller seas must be defined manually, thus for the region of the Dead Sea and the Caspian Sea not fraction lake but fraction ocean is calculated.

For fr_land ¹⁰ and fr_ocean ¹¹ larger than a half, the lake depth is set to undefined. A default value for the lake depth is used for grid elements with a lake fraction ¹² larger than a half and a negative lake depth. Additionally a maximum and minimum lake depth is defined. Included is also a manual correction of the depth of Lake Constance.

⁸J.M. Hollisa, J. Hannamb and P.H. Bellamyb, February 2012, Empirically-derived pedotransfer functions for predicting bulk density in European soils, European Journal of Soil Science, 63, 96109 doi: 10.1111/j.1365-2389.2011.01412.x

⁹J.H.M. Woesten, A. Lilly, A. Nemes and C. Le Bas, Development and use of a database of hydraulic properties of European soils, Geoderma, Volume 90, Issues 34, July 1999, Pages 169-185, doi: 10.1016/S0016-7061(98)00132-3.

 $^{^{\}rm 10} derived$ from the land use data

 $^{^{11}}$ derived from the land use data

 $^{^{\}rm 12} derived$ from the lake data set

Consistency check of albedo data

The consistency check of the albedo data concerns land pixels that have a albedo smaller than 0.07. For these pixels a weighted bilinear interpolation is performed. Only land points are used for the interpolation, if there is no surrounding land point a warning message is printed. Values that are still too small receive a soiltype dependent albedo. This is done for all three wavelengths.

Consistency check of NDVI data

The next consistency check is performed with the normalized difference vegetation index (NDVI). The NDVI values are set to undefined for water grid points. Additionally, values that are smaller than a predefined value are set to exactly this value.

Consistency check of the temperature climatology

The consistency check of the temperature climatology contains a height correction and is only performed for the finer resolved temperature climatology (e.g. it_cl_type = 1). The temperature is set to undefined for all the sea points. For land points that have a valid temperature, it is adjusted to the height. This is done by considering a constant temperature rate of 0.65 K per 100m ($\frac{dT}{dh} = -\frac{0.65K}{100m}$).

Target points that do not contain temperature values larger than zero are filled with surrounding values. First a valid point is looked for in the surrounding 3×3 grid box. If still no valid point can be found, it is searched along the longitude, and if nothing else helps the nearest neighbor is tried.

Consistency check of all other fields

All other fields are assumed to be independent and are written to the output file exactly as they were read in. A special treatment applies to the ISA, AHF, EMISS and S_ORO fields. Whenever their respective namelist input file is missing in the working directory where extpar_consistency_check is executed these fields are not added to the output file. An exception to this rule applies to the ISA and AHF fields which are added to the output file if the logical switch *l_terra_urb* is set to .TRUE. in the *INPUT_LU* namelist; see section 3.2.2 for more details.

Definition of special points

Be aware that the definition of special points has only been tested for the COSMO grid and can only be used if the FAO raw soil type is used. At the moment there are three special points (1: Falkenberg, 2: Waldstation, 3: Lindenberg). At each of these points, values for soiltype_sp, z0_sp, rootdp_sp, plcovmn_sp, plcovmx_sp, laimx_sp can be explicitly set by the user. The coordinates of the special point are also user specified. If no special treatment at these points is desired the number_special_points must be set to zero (see table 11). If no special treatment is desired at all, the integer switch i_lsm_treatment can be set to 1 instead of 2.

number_special_points	Treatment of special points
0	NO treatment of special points
1	special treatment of Falkenberg
2	special treatment of Falkenberg and Waldstation
3	special treatment of Falkenberg, Waldstation and Lindenberg

Table 11: Usage of the namelist parameter number_special_points.

Reduced main memory usage

Since Exptar Version 5.4 a new feature was introduced which allows the running of extpar_consistency_check for very high resolution global grids without any restrictions on the hardware memory specifications. A POSIX mmap based implementation of disk caching arrays is used to use main memory as much as possible and, if more memory is required, the duty to handle this request is delegated to the kernel.

A requirement to run this properly is the provision of swap space in the expected total memory use. With this technique we could process a global R2B11 ICON grid (around 1.25 km grid resolution) on a server with 256 GB main memory. Of course processing gets quite slow, but is still in the order of a couple of cups of coffee.

The feature can be enabled with the namelist variable

 $l_use_array_cache = .TRUE$. in namelist $extpar_consistency_check_io$. The namelist variable default is $l_use_array_cache = .FALSE$., which is selecting the standard heap allocation by Fortran's ALLOCATE statement.

Writing output

The final results are written into a netcdf file. The output file name can be specified in the namelist 'INPUT_CHECK'.

Since Extpar Version 5.4 the output possibilities have been extended for ICON only. The Extpar output procedure for COSMO did not change with Version 5.4. As ICON and a lot of its associated tools (eg. CDO, DWD icontools) are already using a single abstract interfacing library CDI, a re-implementation for the final Extpar output procedure with CDI to prepare for future developments is provided. Note, that this re-implementation replaces the former writing-routine completely. For a detailed description of CDI look at

https://code.mpimet.mpg.de/projects/cdi.

Used namelist files and data in-/output

- namelists files: INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID, INPUT_CHECK, INPUT_*
- data input: all buffer files from the Extpar modules defined in the 'INPUT_*' namelist files
- data output: netCDF containing all external parameters (/extpar_consistency_check_io/ netcdf_output_filename)

4 Python modules

4.1 General workflow

The general workflow of all Python modules is the same. An exemplary workflow of the Python modules is described below:

At the beginning of the program information about the environment on which Extpar is running is written to the logfile and all left-overs from prior executions of the same Extpar module are deleted. In a next step each parameter from the namelist 'namelist.py' is checked for correctness as well as assigned to an internal variable for later use in the program. The specifaction about the target grid is directly read from the Fortan namelist-files 'INPUT_grid_org. The next step in the modules involves the generation of all necessary meta-data for the buffer files and the write of a namelist files in the style of a Fortran namelist, containing all information needed for the consistency_check at the end. In case of a COSMO target grid, a grid specification file is written, that is later used by CDO for the interpolation.

After this is all setup, the most compute-intensive parts like the remapping to the target grid or data modifications are done using CDO. The Python program launches a subshell executing the CDO in it. The output from CDO is reshaped in order to fit the dimensions of the buffer files. After the reshape, the fields and its corresponding metadata is written to a netCDF buffer file. The last step of the programme again deletes all intermediate netCDF or other files written during runtime, that do not serve any purpose.

Module-specific modifications or additional computations are described in the paragraph *Data processing* of each Python module.

Namelist

The namelist 'namelist.py' contains the Python dictionaries 'input_alb', 'input_tclim', 'input_emiss', 'input_ahf', 'input_isa' and 'input_edgar'. These dictionaries replace their corresponding Fortran namelist files 'INPUT_*'.

'input_alb' provides information about the albedo data type and the paths and filenames of the input/output data.

'input_tclim' contains a switch to determine the type of data (coarse or fine) as well as the paths and filenames of the input/output data.

'input_emiss' contains a switch to determine the type of emissivity data (full range or long-wave) and the filename and paths of the input/output data.

'input_ndvi only provides information about the the path and the filenames of the input/output data. 'input_era only provides information about the the path and the filenames of the input/output data.

'input_isa contains a switch determine the type of ISA data and provides information about the the path and the filenames of the input/output data.

'input_ahf contains a switch determine the type of AHF data and provides information about the the path and the filenames of the input/output data.

'input_edgar only provides information about the the path and the filenames of the input/output data.

4.2 extpar_alb_to_buffer

4.2.1 Short description of the subprogram extpar_alb_to_buffer

The executable *extpar_alb_to_buffer* allows the aggregation of two different kinds of albedo data to the target grid. The first kind is a climatology of monthly values of total albedo derived from MODIS satellite data for the 3 spectral bands visible, near infrared and ultraviolet. The second kind contains information for soil albedo only in dry and saturated conditions. It originates from the Community Land Model¹³.

¹³https://svn-ccsm-inputdata.cgd.ucar.edu/trunk/inputdata/lnd/clm2/rawdata/mksrf.soilcol.081008.nc Lawrence, P. J. and T. N. Chase (2007). "Representing a new MODIS consistent land surface in the Community Land Model (CLM 3.0)." Journal of Geophysical Research-Biogeosciences 112(G1).

Table 3.3 in: Oleson, K.W., D.M. Lawrence, G.B. Bonan, M.G. Flanner, E. Kluzek, P.J. Lawrence, S. Levis, S.C. Swenson, P.E. Thornton, A. Dai, M. Decker, R. Dickinson, J. Feddema, C.L. Heald, F. Hoffman, J.-F. Lamarque, N. Mahowald, G.-Y. Niu,

Data processing

The data is remapped to the target grid using the *distance-weighted average* interpolation. CDO first generates the weights for the interpolation from one of the input files and then applies these weights to all input files. After the interpolation took place, all values in the range of -100000 - 0.02 are set to 0.02 to prevent unrealistic data-points. All other steps in extpar_alb_to_buffer are following the general workflow of the Python scrips.

4.2.2 Used namelist files and data in-/output

- namelist files: namelist.py (dict: input_alb), INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID
- generate namelist: INPUT_ALB
- data input: month_alb.nc, month_alnid.nc, month_aluvd.nc, global_soil_albedo.nc
- data output: buffer file with albedo data (input_alb: alb_buffer_file)

4.3 extpar_cru_to_buffer

4.3.1 Short description of the subprogram extpar_cru_to_buffer

The executable <code>extpar_cru_to_buffer</code> aggregates the temperature climatology of the Climate Research Unit (CRU) to the target grid. The namelist 'namelist.py' gives the information of the path and the name of the raw temperature climatology data file. Additionally, the filename for the buffer is provided. There is an integer switch (it_cl_type), which allows the choice between a newer higher resolved data set for land surfaces only (1) and an older coarser raw data set for sea surfaces in combination with the higher resolved data set over land (2). Aggregation of the coarse data set over land surfaces is no longer supported since Extpar Version 5.4.

Data processing

The data processing with CDO for it_cl_type = 1 involves 4 steps:

- 1. Set seapoints in the data to missing value.
- 2. Extract the fields 'HSURF' from the fine data set.
- 3. Merge the fields from step 1 and step 2.
- 4. Remap data from step 3 to the target grid using distance-weighted average interpolation.

The data processing with CDO for it_cl_type = 2 involves 5 steps:

- 1. Convert coarse data from Celsius to Kelvin, calculate yearly mean values and remap coarse data to the grid of the higher resolved data set.
- 2. Take landpoints from the fine data set and the seapoints from the data processed in step 1.
- 3. Extract surface height from the buffer file of *extpar_topo_to_buffer*
- 4. Smooth data processed in step 2 and remap to target grid using *distance-weighted average* interpolation.
- 5. Correct data processed in step 4 with the surface height extracted in step 3.

All subsequent processing on the data follows the general workflow of the Python scripts.

T. Qian, J. Randerson, S. Running, K. Sakaguchi, A. Slater, R. Stockli, A. Wang, Z.-L. Yang, Xi. Zeng, and Xu. Zeng, 2010: Technical Description of version 4.0 of the Community Land Model (CLM). NCAR Technical Note NCAR/TN-478+STR, National Center for Atmospheric Research, Boulder, CO, 257 pp.

4.3.2 Used namelist files and data in-/output:

- namelists files: namelist.py (dict: input_tclim), INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID
- generate namelist: INPUT_TCLIM
- data input: absolute_hadcrut3.nc, CRU_T2M_SURF_clim.nc, CRU_T_SOIL_clim.nc, orography_buffer_file (it_cl_type = 2 only)
- Output: buffer file with CRU data (input_tclim: t_clim_buffer_file)

4.4 extpar_emiss_to_buffer

4.4.1 Short description of the subprogram extpar_emiss_to_buffer

The executable *extpar_emiss_to_buffer* aggregates CAMEL (Combined ASTER and MODIS Emissivity for Land) data to the target grid. For the aggregation of the emissivity the namelist 'namelist.py' provides the path and the file name of the input data. The buffer file name is defined as well. There exists the integer switch (iemiss_type) to determine whether one wants to use the broad band emissivity for the 3.6 and 14.3 micron spectral range (1) or the broad band emissivity between 8.0 and 13.5 micron spectral range (2).

Data processing

After the generation of the interpolation weights artificial low values below 0.5 are set to -999. In a subsequent processing step -999 is set to the value for missing data. In order to not have missing data in the field to interpolate, all missing values are set to the values of its nearest neighbour. The last step involves the *first order conservative* interpolation to the target grid. After the remapping with CDO two additional fields are computed:

- EMISS_MAX, the maximum EMISS value over 12 months
- EMISS_MRAT, the monthly ratio with respect to the maximum EMISS

4.4.2 Used namelist files and data in-/output:

- namelists files: namelist.py (dict: input_emiss) INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID
- generate namelist: INPUT_EMISS
- data input: CAM_bbe_full_2010-2015nc or CAM_bbe_lw_2010-2015nc
- Output: buffer file with CAMEL data (input_emiss: emiss_buffer_file)

4.5 extpar_ndvi_to_buffer

4.5.1 Short description of the subprogram extpar_ndvi_to_buffer

The executable <code>extpar_ndvi_to_buffer</code> aggregates NDVI data (Normalized Differential Vegetation Index) to the target grid. The namelist 'namelist.py' only contains the path and the file name of the raw NDVI data. No other parameters can be set.

For the aggregation of the normalized differential vegetation index the namelist 'namelist.py' is simple. It contains the path and the filename of the raw data set, as well as the names of the buffer. No other parameters can be set.

Data processing

The remapping to the target grid uses the *first order conservative* interpolation. After the remapping with CDO two additional fields are computed:

- NDVI_MAX, the maximum NDVI value over 12 months
- NDVI_MRAT, the monthly ratio with respect to the maximum NDVI

4.5.2 Used namelist files and data in-/output:

- namelists files: namelist.py (dict: input_ndvi), INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID
- generate namelist: INPUT_NDVI
- data input: NDVI_1998_2003.nc
- Output: buffer file with NDVI data (input_ndvi: ndvi_buffer_file)

4.6 extpar_era_to_buffer

4.6.1 Short description of the subprogram extpar_era_to_buffer

The executable *extpar_era_to_buffer* aggregates ERA data (T2M, SST, W_SNOW and ORO) to the target grid. It replaces the two NetCDF-Files generated by ICON-REMAP at DWD. Note that this executable is for Icon-grids only.

For the aggregation of the ERA climatologies the namelist 'namelist.py' is simple again. It contains the type of ERA climatology (ERA5 (1) or ERA-I (2)) the path and the filenames of the raw data sets, as well as the names of the buffer. No other parameters can be set.

Data processing

The remapping to the target grid uses the *first order conservative* interpolation. After the remapping with CDO the field *W_SNOW* is scaled by a factor 1000. No other processing steps take place.

4.6.2 Used namelist files and data in-/output:

- namelists files: namelist.py (dict: input_era), INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID
- generate namelist: INPUT_ERA
- data input: ERA5_ORO_1990.nc, ERA5_SD_1990_2019.nc, ERA5_SST_1990_2019.nc and ERA5_T2M_1990_2019.nc
 ERA-I_ORO_1986.nc, ERA-I_SD_1986_2015.nc, ERA-I_SST_1986_2015.nc and ERA-I_T2M_1986_2015
- Output: buffer file with ERA data (input_era: era_buffer_file)

4.7 extpar_isa_to_buffer

4.7.1 Short description of the subprogram extpar_isa_to_buffer

The executable *extpar_isa_to_buffer* allows the aggregation or interpolation of data on the fraction of impervious surface area needed by TERRA_URB to the target grid.

For the aggregation of the ISA the namelist 'namelist.py' is simple again. It contains the type of ISA (NOAA (1) or EEA (2)) the path and the filenames of the raw data sets, as well as the names of the buffer. No other parameters can be set. Note that the underlying processing does not differ between different types of ISA

The remapping to the target grid uses the *bilinear* interpolation. No other processing steps take place.

4.7.2 Used namelist files and data in-/output:

- namelists files: namelist.py (dict: input_isa), INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID
- generate namelist: INPUT_ISA
- data input: EEA_ISA_16bit_lonlat.nc(isa_type=2), NOAA_ISA_16bit_lonlat.nc (isa_type=1)
- Output: buffer file with ISA data (input_isa: isa_buffer_file)

4.8 extpar_ahf_to_buffer

4.8.1 Short description of the subprogram extpar_ahf_to_buffer

The executable *extpar_ahf_to_buffer* allows the aggregation or interpolation of data on the anthropogenic heat flux needed by TERRA_URB to the target grid.

For the aggregation of the AHF the namelist 'namelist.py' is simple again. It contains the type of AHF (2.5min (1) or 30sec (2)) the path and the filenames of the raw data sets, as well as the names of the buffer. No other parameters can be set. Note that the underlying processing does not differ between different types of AHF

The remapping to the target grid uses the *bilinear* interpolation. No other processing steps take place.

4.8.2 Used namelist files and data in-/output:

- namelists files: namelist.py (dict: input_ahf), INPUT_grid_org, INPUT_COSMO_GRID, INPUT_ICON_GRID
- generate namelist: INPUT_AHF
- data input: AHF_2006_2.5min_lonlat.nc (ahf_type=1),AHF_2006_NOAA_30sec_lonlat.nc (ahf_type=2)
- Output: buffer file with AHF data (input_ahf: ahf_buffer_file)

4.9 extpar_edgar_to_buffer

4.9.1 Short description of the subprogram extpar_edgar_to_buffer

The executable *extpar_edgar_to_buffer* allows the interpolation of global emission data for black carbon, organic carbon and sulfur dioxide needed for the 2D-Aerosol in ICON to the target grid.

The namelist contains only the path to the raw data, the raw data file names and the name of the buffer file.

The remapping to the target grid uses the *first order conservative* interpolation. No other processing steps take place.

4.9.2 Used namelist files and data in-/output:

- namelists files: namelist.py (dict: input_edgar), INPUT_grid_org, INPUT_ICON_GRID
- generate namelist: INPUT_edgar
- data input: v8.1_FT2022_AP_NH3_2022_TOTALS_flx.nc, v8.1_FT2022_AP_OC_2022_TOTALS_flx.nc,
 - v8.1_FT2022_AP_BC_2022_TOTALS_flx.nc,
 - v8.1_FT2022_AP_NOx_2022_TOTALS_flx.nc,
 - v8.1_FT2022_AP_SO2_2022_TOTALS_flx.nc
- Output: buffer file with EDGAR data (input_edgar: edgar_buffer_file)

4.10 extpar_cdnc_to_buffer

4.10.1 Short description of the subprogram extpar_cdnc_to_buffer

The executable <code>extpar_cdnc_to_buffer</code> allows the interpolation of climatology data for cloud droplet number needed for the Cloud-Aerosol in ICON to the target grid.

The namelist contains only the path to the raw data, the raw data file names and the name of the buffer file

The remapping to the target grid uses the *first order conservative* interpolation. No other processing steps take place.

4.10.2 Used namelist files and data in-/output:

- namelists files: namelist.py (dict: input_cdnc), INPUT_grid_org, INPUT_ICON_GRID
- generate namelist: INPUT_cdnc
- data input: cdnc_climatology_Q06.nc
- Output: buffer file with cloud droplet number data (input_cdnc: cdnc_buffer_file)

5 Current limitations

5.1 General limitations

The EXTPAR software is subject to several limitations:

- The ASTER domain can only be used from 60°N to 60°S. Be aware that an additional border of several gridpoints is needed if the topographically corrected parameters are desired. If the ASTER domain is exceeded a warning message is printed and the program *extpar_topo_to_buffer* is aborted.
- The ASTER data shows some deficits, which are listed below:
 - Beyond 60 degrees north and south, the ASTER raw data set features several areas where no value is available e.g., over Finland (private communication with HIRLAM).
 - Some bogus regions may appear in complex topography. One of these regions is located near Grindelwald in Switzerland.
 - The ASTER data are subject to artefacts of the satellite fly-over bands. Discontinuities can
 be spotted at the borders of such bands. In high latitudes these bands are better visible than
 in the low latitudes.
 - As the correction of these deficits are time consuming no effort has been expended to remove these.
 - The ASTER data might be subject to a shift of a half gridpoint (15 meters) in both directions.
- There is no 3 km filtered ASTER or MERIT/REMA data set to derive the subgrid scale orography (SSO) parameters and the roughness length (z0) for ASTER.
- The HWSD raw data is in a test phase. Furthermore a new Version of Int2lm and TERRA is needed to make use of these data sets.
- The subsoil can only be used if the HWSD data is used for the topsoil. If the FAO and the HWSD data are combined a warning message is printed and the ldeep_soil parameter is set to .FALSE.
- The special points are only tested for the COSMO grid. Also it is not possible to use these corrections if the soil raw data set is HWSD.
- Array-caching in the consistency_check is only supported for GCC compiler.
- CAMS aersosl data iaot_type = 5 is only support for Intel compiler.

Extpar uses 3 types of namelists in order to determine in which way data is processed.

- Fortran namelists (INPUT_*)
- Python dictionaries (input_* in namelist.py)
- Fortran namelists written by Python scripts

Whereas for the Fortran namelists and the Python dictionaries the user can specify parameters and filenames, the Fortran namelists generated during runtime by the Python scripts do not allow any user interaction.

6.1 Namelist files

Namelist file	Purpose	Made by script	Used by program
INPUT_grid_org	define target grid type	runscript	extpar_consistency_check
			extpar_aot_to_buffer
			extpar_landuse_to_buffer
			extpar_topo_to_buffer
			extpar_cru_to_buffer
			extpar_ndvi_to_buffer
			extpar_soil_to_buffer
			extpar_flake_to_buffer
			extpar_isa_to_buffer
			extpar_ahf_to_buffer
			extpar_emiss_to_buffer
			extpar_hwsdART_to_buffe
INPUT_COSMO_GRID	define target domain for COSMO grid	runscript	extpar_consistency_check
	_		extpar_aot_to_buffer
			extpar_landuse_to_buffer
			extpar_topo_to_buffer
			extpar_cru_to_buffer
			extpar_ndvi_to_buffer
			extpar_soil_to_buffer
			extpar_flake_to_buffer
			extpar_isa_to_buffer
			extpar_ahf_to_buffer
			extpar_emiss_to_buffer
			extpar_hwsdART_to_buffe
INPUT_ICON_GRID	define target domain for ICON grid	runscript	extpar_consistency_check
			extpar_aot_to_buffer
			extpar_landuse_to_buffer
			extpar_topo_to_buffer
			extpar_cru_to_buffer
			extpar_ndvi_to_buffer
			extpar_soil_to_buffer
			extpar_flake_to_buffer
			extpar_isa_to_buffer
			extpar_ahf_to_buffer
			extpar_emiss_to_buffer
INPUT_ORO	settings for orography data	runscript	extpar_topo_to_buffer

Namelist file	Purpose	Made by script	Used by program
INPUT_OROSMOOTH	settings for orography smooth-	runscript	extpar_topo_to_buffer
	ing		
INPUT_RADTOPO	settings for generating topo-	runscript	extpar_topo_to_buffer
	graphical shading fields		
INPUT_SCALE_SEP	settings to control scale separa-	runscript	extpar_topo_to_buffer
	tion for SSO an Z0 calculation		
INPUT_LU	settings for landuse data	runscript	extpar_landuse_to_buffer
INPUT_AOT	settings for aerosol data	runscript	extpar_aot_to_buffer
INPUT_TCLIM	settings for temperature data	extpar_cru	extpar_consistency_check
		to_buffer	
INPUT_NDVI	settings for NDVI data	extpar_ndvi	extpar_consistency_check
		to_buffer	
INPUT_SOIL	settings for soil data	runscript	extpar_soil_to_buffer
INPUT_FLAKE	settings for lake data	runscript	extpar_flake_to_buffer
INPUT_ALB	settings for albedo data	extpar_albedo	extpar_consistency_check
		to_buffer	
INPUT_ISA	settings for fraction of impervi-	extpar_isa_to_buf	fæxtpar_consistency_check
	ous surface area data		
INPUT_AHF	settings for anthropogenic heat flux data	extpar_ahf_to_bu	ffextpar_consistency_check
INPUT_EMISS	settings for emissivity data	extpar_emiss	extpar_consistency_check
	,	to_buffer	
INPUT_hwsdART	settings for HWSD USDA data	extpar_hwsdAR	<u> </u>
	<u> </u>	to_buffer	
INPUT_edgar	settings for EDGAR data	extpar_edgar	extpar_consistency_check
		to_buffer	_
INPUT_CDNC	settings for cdnc data	extpar_cdnc	extpar_consistency_check
	_	to_buffer	
INPUT_ERA	settings for ERA data	extpar_era	extpar_consistency_check
		to₋buffer	
INPUT_CHECK	settings for the consistency	runscript	extpar_consistency_check
	check		

6.2 Grid definition

The specification of the model type (COSMO or ICON) is done in the namelist file INPUT_grid_org, the detailed target grid description for the model domain has to be provided in the namelists files INPUT_COSMO_GRID or INPUT_ICON_GRID.

6.2.1 general

NAMELIST /grid_def/ (INPUT_grid_org)

The namelist /grid_def/ defines the target grid type and the filenames with the namelists of the detailed target grid definition.

Parameter	Type	Default	Unit	Description
igrid_type	integer			target grid type, 1 for ICON, 2 for
				COSMO
domain_def_namelist	character			namelist file with domain definition
domain_refinement	character			namelist file with domain refinement
				definition (e.g. for the ICON grid)

6.2.2 Icon

NAMELIST /icon_grid_info/ (INPUT_ICON_GRID)

The namelist /icon_grid_info/ specifies the filenames and the directory of the Icon grid files with the coordinates of the Icon grid.

Parameter	Type	Default	Unit	Description
icon_grid_dir	character			path to directory which contains the
				ICON grid file with the coordinates
icon_grid_nc_file	character			filename of the ICON grid file with the
	(max_dom)			coordinates

6.2.3 COSMO

NAMELIST /Imgrid/ (INPUT_COSMO_GRID)

The COSMO grid is defined by a rotated latlon-grid.

Parameter	Type	Default	Unit	Description
pollon	real	-170.	deg	longitude of the rotated north pole (in
				degrees, $E > 0$)
pollat	real	32.5	deg	latitude of the rotated north pole (in
				degrees, $N > 0$)
polgam	real	0.	deg	longitude (in the rotated system) of the
				geographical north pole
dlon	real	0.08	deg	grid point distance in zonal direction
				(in degrees)
dlat	real	0.08	deg	grid point distance in meridional di-
				rection (in degrees)
startlon_tot	real	-1.252	deg	transformed longitude of the lower left
				grid point of the total domain (in de-
				grees, $E > 0$)
startlat_tot	real	-7.972	deg	transformed latitude of the lower left
				grid point of the total domain (in de-
				grees, $N > 0$)
ie_tot	integer	51		number of grid points in zonal direc-
				tion
je_tot	integer	51		number of grid points in meridional
				direction
ke_tot	integer	0		number of grid points in vertical direc-
				tion

6.3 Orography

NAMELIST /oro_runcontrol/ (INPUT_ORO)

Parameter	Type	Default	Unit	Description
lcompute_sgsl	logical	.false.		switch to activate subgrid-slope calculation

NAMELIST /orography_raw_data/ (INPUT_ORO)

Parameter	Type	Default	Unit	Description
itopo_type	integer			switch to choose an orography raw
				data set; 1 GLOBE, 2 ASTER, 3 MER-
				IT/REMA
lsso_param	logical			switch to choose if SSO parameters
				should be generated or not
raw_data_orography_path	character			path to orography raw data
ntiles_column	integer	GLOBE:		number of tile columns of desired re-
		4		gion
		ASTER,		
		MER-		
		IT/REMA:		
		X		
ntiles_row	integer	GLOBE:		number of tile rows of desired region
		4		
		ASTER,		
		MER-		
		IT/REMA:		
(1)		X		
topo_files	character			filenames of GLOBE (16 tiles) / ASTER
				(240 tiles)/ MERIT/REMA (72 tiles)
				raw data sets
lsubtract_mean_slope	logical	.FALSE.		treatment of mean slope in computa-
		for op-		tion of SSO parameters for ICON
		erational		
		NWP-		
		ICON		

NAMELIST /orography_io_extpar/ (INPUT_ORO)

Parameter	Type	Default	Unit	Description
orography_buffer_file	character			name for orography buffer file
orography_output_file	character			name for orography output file

NAMELIST /sgsl_io_extpar/ (INPUT_ORO)

Parameter	Type	Default	Unit	Description
lpreproc_oro	logical	.false.		read S_ORO from existing NetCDF
				(.false.) or preprocess from raw topog-
				raphy datasets (.true.)
sgsl_files	character			filenames of raw data tiles to be used
				S_ORO_A10 to S_ORO_P10 (GLOBE) or
				S_ORO_T001 to S_ORO_T240

${\bf NAMELIST\:/orography_smoothing/\:(INPUT_OROSMOOTH)}$

Parameter	Type	Default	Unit	Description
lfilter₋oro	logical	FALSE		Cosmo-only: switch for orogaphy
				smoothing
ilow_pass_oro	integer	0		type of orogaphy smoothing and sten-
				cil width

Parameter	Type	Default	Unit	Description
numfilt_oro	integer	1		number of filter applications
eps_filter	real	10		smoothing parameter ("strength" of
				the filtering)
ifill_valley	integer	1		fill valleys before or after oro smooth-
				ing (1: before, 2: after)
rfill_valley	real	0	m	mask for valley filling (threshold
				value)
ilow_pass_xso	integer	1		type of orogaphy eXtra SmOothing
				and stencil width (for steep orography)
numfilt_xso	integer	1		number of applications of the eXtra fil-
				ter
lxso_first	logical	FALSE		eXtra SmOothing before or after orog-
				raphy smoothing (TRUE/FALSE)
rxso_mask	real	0	m	mask for eXtra SmOothing (threshold
				value)

NAMELIST /radtopo/ (INPUT_RADTOPO)

Parameter	Type	Default	Unit	Description
Iradtopo	logical			Switch for radiation corrected topography parameters. Not recommended to use if orographical smoothing is false and smoothing is performed in Int2lm later, because of resulting inconsistencies.
nhori	integer	24		Number of horizon angles
radius	integer	40000	m	Icon-only: Radial distance considered for computation of horizon
min_circ_cov	integer	1	-	Icon-only: Number of gridcells to be skipped at circumference of circle. A value of 1 considers all points, whereas a value of 5 only consider every fifth point at the circumference. Note that the effect of this switch is dependent on the resolution of the grid as well on the radius choosen.
max_missing	real	0.9	-	Icon-only: Upper limit for fraction of missingness for the horizon parameter. Grid-cells with values above will be set to 0.
itype_scaling	integer	2	-	Icon-only: Power of the caling factor <i>SIN(horizon-angle)</i> applied to the geometric skyview factor to account for the anisotropic nature of longwave radiation.

${\bf NAMELIST\ / scale_separated_raw_data/\ (INPUT_SCALE_SEP)}$

Parameter Type Default Unit Description

Parameter	Type	Default	Unit	Description
lscale_separation	logical			Switch for scale separation. It can only
				be used in combination with GLOBE as
				raw data set.
raw_data_scale_sep_path	character			path to 3 km filtered topography
scale_sep_files	character			filename of 3 km filtered topography

6.4 Land Use data

NAMELIST /lu_raw_data/ (INPUT_LU)

Parameter	Type	Default	Unit	Description
raw_data_lu_path	character			path to landuse data
raw_data_lu_filename	character			filename of landuse raw data
i_landuse_data	integer			switch to choose a land use raw data
				set; 1 Globcover2009, 2 GLC2000, 3
				GLCC, 5 ESA CCI-LC, 6 Ecoclimap-SG
l_use_corine	logical	.false.		switch to use corine landuse dataset;
				only possible if i_landuse_data = 1
ilookup_table_lu	integer			switch to choose a lookup table
				GLC2000 and GLCC:
				1: operational settings of GME (Ritter,
				2007)
				2: operational settings of COSMO (Heise, 2005)
				3: experimental setting, analog to look-
				up tables of ECOCLIMAP (Asensio
				2010)
				GLOBCOVER 2009:
				1: operational settings (Asensio, 2011)
				2: experimental settings, analog to
				look-up tables of ECOCLIMAP (Asen-
				sio 2010)
				ESA CCI-LC:
				1: experimental settings (Helmert,
				2019)
				Ecoclimap-SG:
				1: Globcover analogue with added
				LCZs from Oke
ntiles_globcover	integer	6		number of tiles for GLOBCOVER data
ncolumn_tiles	integer	6.1		number of columns in tile matrix
l_terra_urb	logical	.false.		switch to use TERRA-URB (see 3.2.2);
				only possible if i_landuse_data = 6

NAMELIST /glcc_raw_data/ (INPUT_LU)

Parameter	Type	Default	Unit	Description
raw_data_glcc_path	character			path to glcc data
raw_data_glcc_filename	character			filename of glcc raw data
ilookup_table_glcc	integer			switch to choose a lookup table
				1: operational settings of GME (Ritter,
				2007)

Parameter	Type	Default	Unit	Description
				2: operational settings of COSMO
				(Heise, 2005)
				3: experimental setting, analog to look-
				up tables of ECOCLIMAP (Asensio
				2010)

NAMELIST /glcc_io_extpar/ (INPUT_LU)

Parameter	Type	Default	Unit	Description
glcc_buffer_file	character			name for glcc buffer file

6.5 Aerosol optical depth

NAMELIST /aerosol_raw_data/ (INPUT_AOT)

Parameter	Type	Default	Unit	Description
raw_data_aot_path	character			path to aerosol raw data
raw_data_aot_filename	character			filename of aerosol raw data
iaot_type	integer	1		index to specify AOD raw data set: 1:Tegen 2:AeroCom 3:MACC-II
				4:MACv2 5:CAMS

NAMELIST /aerosol_io_extpar/ (INPUT_AOT)

Parameter	Type	Default	Unit	Description
aot_buffer_file	character			name for aerosol buffer file

6.6 Climatological 2m temperature

DICT input_tclim (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_t_clim_path	character			path to T2m climatology data
raw_data_t_clim_coarse	character			filename of coarse T2m climatology
				data
raw_data_t_clim_fine	character			filename of fine T2m climatology data
it_cl_type	integer			switch to choose between the new and
				fine (1) and the old and coarse over sea
				and the fine over land (2) raw data set.
				Note that the fine data set (1) is topo-
				graphically corrected.
t_clim_buffer_file	character			name for t_clim buffer file

6.7 NDVI data

DICT input_ndvi (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_ndvi_path	character			path to ndvi raw data
raw_data_ndvi_filename	character			filename of ndvi raw data
ndvi_buffer_file	character			name for ndvi buffer file

6.8 EDGAR data

DICT input_edgar (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_edgar_path	character			path to EDGAR raw data
raw_data_edgar	character			filename of EDGAR black carbon raw
filename_bc				data
raw_data_edgar	character			filename of EDGAR organic carbon
filename_oc				raw data
raw_data_edgar	character			filename of EDGAR sulfur dioxide raw
filename_so2				data
raw_data_edgar	character			filename of EDGAR ammonia raw
filename_nh3				data
raw_data_edgar	character			filename of EDGAR nitrogen oxides
filename_nox				raw data

6.9 CDNC data

DICT input_cdnc (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_cdnc_path	character			path to cdnc raw data
raw_data_cdnc_filename	character			filename of cdnc raw data

6.10 hwsdART data

NAMELIST /hwsdART_nml/ (INPUT_hwsdART)

Parameter	Type	Default	Unit	Description
raw_data_hwsdART_path	character			path to hwsdART raw data
raw_data_hwsdART_filenar	neharacter			filename of hwsdART raw data
hwsdART_output_file	character			name for hwsdART output file

6.11 Soil data

NAMELIST /soil_raw_data/ (INPUT_SOIL)

Parameter	Type	Default	Unit	Description
isoil_data	integer			switch to choose between the raw soil
				data, 1: FAO, 2: HWSD, 3:HWSD with
				terra mapping
ldeep_soil	logical			switch for the deep soil, can only be set
				to .TRUE. if the top and sub soil are de-
				duced from the HWSD data

Parameter	Type	Default	Unit	Description
raw_data_soil_path	character			path to soil raw data
raw_data_soil_filename	character			filename of soil raw data
raw_data_deep_soil filename	character			filename of deep soil raw data

NAMELIST /soil_io_extpar/ (INPUT_SOIL)

Parameter	Type	Default	Unit	Description
soil_buffer_file	character			name for soil buffer file
soil_buffer_file_consistent	character			name for soil buffer file after consis-
				tency check
soil_output_file_consistent	character			name for soil output file after consis-
				tency check

NAMELIST /HWSD_index_files/ (INPUT_SOIL)

Parameter	Type	Default	Unit	Description
path_HWSD_index_files	character			path to HWSD lookup tables
lookup_table_HWSD	character			lookup table to convert soiltype index
				from global to TERRA soiltype
HWSD_data	character			lookup table to convert the global
				soiltype in fractions of sand, silt, clay
				and organic carbon and in bulk density
				for the topsoil
HWSD_data_deep	character			lookup table to convert the global
				soiltype in fractions of sand, silt, clay
				and organic carbon and in bulk density
				for the subsoil
HWSD_data_extpar	character			parameter used only for development
				purposes

6.12 Freshwater Lake data

NAMELIST /flake_raw_data/ (INPUT_FLAKE)

Parameter	Type	Default	Unit	Description
raw_data_flake_path	character			path to flake raw data
raw_data_flake_filename	character			filename of flake raw data

NAMELIST /flake_io_extpar/ (INPUT_FLAKE)

Parameter	Type	Default	Unit	Description
flake_buffer_file	character			name for flake buffer file

6.13 Albedo data

DICT input_alb (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_alb_path	character			path to raw albedo data
raw_data_alb_filename	character			filename of the raw albedo data
raw_data_alnid_filename	character			filename of the raw NIR-albedo data
raw_data_aluvd_filename	character			filename of the raw UV-albedo data
ialb_type	integer			switch to indicate albedo type 1:total
				albedo 2:soil albedo 3:as 1 without NI
				and UV fields
alb_buffer_file	character			name for the albedo buffer file

6.14 ISA data

DICT input_isa (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_isa_path	character			path to ISA raw data
raw_data_isa_filename	character			filename of ISA raw data
isa_type	integer			type of used ISA data source
isa_buffer_file	character			name for ISA buffer file

6.15 AHF data

DICT input_ahf (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_ahf_path	character			path to AHF raw data
raw_data_ahf_filename	character			filename of AHF raw data
iahf_type	integer			type of used AHF data source
ahf_buffer_file	character			name for AHF buffer file

6.16 Emissivity parameter

DICT input_emiss (namelist.py)

Parameter	Type	Default	Unit	Description
iemiss_type	integer			switch to choose between full-range (1)
				and long-wave (2) emissivity data
raw_data_emiss_path	character			path to emissivity parameter raw data
raw_data_emiss_filename	character			filenames of emissivity raw data
emiss_buffer_file	character			name for emissivity parameter buffer
				file

6.17 ERA parameter

DICT input_era (namelist.py)

Parameter	Type	Default	Unit	Description
iera_type	integer			type of ERA climatology: ERA5 (1) and
				ERA-I (2)
raw_data_era_path	character			path to ERA raw data

Parameter	Type	Default	Unit	Description
raw_data_era_ORO	character			filenames of ERA ORO raw data
raw_data_era_SD	character			filenames of ERA SD raw data
raw_data_era_T2M	character			filenames of ERA T2M raw data
raw_data_era_SST	character			filenames of ERA SST raw data
era_buffer_file	character			name for era parameter buffer file

6.18 Consistency check

NAMELIST /extpar_consistency_check_io/ (INPUT_CHECK)

Parameter	Type	Default	Unit	Description
l_use_array_cache	flag	F		flag indicating whether mmap-caching is used
				(reduced memory con-
				sumption, but longer
				runtime)
netcdf_output_filename	character			filename for netcdf out-
				put filename
i_lsm_data	integer			integer switch to choose if
				an external land sea mask
				is desired or not. 0: no
				external land sea mask,
				1: use external land sea
				mask
land_sea_mask_file	character			name of the file which can
				be used as the external
				land sea mask.
number_special_points	integer			number of points that
				should be treated spe-
				cially (maximal value: 3,
				if no special treatment is
				desired choose 0).
lwrite_netcdf	logical	T		flag indicating whether
				NetCDF output for
	<u> </u>			COSMO grid is desired.
tile_mode	integer	0		if activated tile_mode=1
				process output for ICON
10.1	1 . 1			tile structure
lflake_correction	logical	T		if activated then fr_lake
				values of grid points next
				to ocean are set to ocean
				values the lake depth
				value is set to undefined. This is the default behav-
				ior in EXTPAR version
				I I
				4.0, but not in DWD EXTPAR version 2.10.
				EATTAK VEISION 2.10.

NAMELIST /special_points/ (INPUT_SP_1)

Modifications for Falkenberg.

Parameter	Type	Default	Unit	Description
lon_geo_sp	real	14.115	deg	longitude coordinate of the special
			east	point
lat_geo_sp	real	52.156	deg	latitude coordinate of the special point
			north	
soiltype_sp	real	3.0	-	soiltype of the special point
z0_sp	real	0.03	m	roughness lenght of the special point
rootdp_sp	real	0.6	m	rooting depth of the special point
plcovmn_sp	real	0.55	1	plant cover minimum of the special
				point
plcovmx_sp	real	0.8	1	plant cover maximum of the special
				point
laimn_sp	real	0.5	1	leaf area index minimum of the special
				point
laimx_sp	real	2.5	1	leaf area index maximum of the special
				point
for_d_sp	real		1	ground fraction covered by deciduous
				forest of the special point
for_e_sp	real		1	ground fraction covered by evergreen
				forest of the special point
fr_land_sp	real		1	fraction land cover of the special point

NAMELIST /special_points/ (INPUT_SP_2)

Modifications for Waldstation.

Parameter	Type	Default	Unit	Description
lon_geo_sp	real	13.954	deg	longitude coordinate of the special
			east	point
lat_geo_sp	real	52.186	deg	latitude coordinate of the special point
			north	
soiltype_sp	real	3.	-	soiltype of the special point
z0_sp	real	0.78	m	roughness lenght of the special point
rootdp_sp	real	0.6	m	rooting depth of the special point
plcovmn_sp	real	0.79	1	plant cover minimum of the special
				point
plcovmx_sp	real	0.81	1	plant cover maximum of the special
				point
laimn_sp	real	3.0	1	leaf area index minimum of the special
				point
laimx_sp	real	4.0	1	leaf area index maximum of the special
				point
for_d_sp	real		1	ground fraction covered by deciduous
				forest of the special point
for_e_sp	real		1	ground fraction covered by evergreen
				forest of the special point
fr_land_sp	real		1	fraction land cover of the special point

NAMELIST /special_points/ (INPUT_SP_3)

Modifications for Lindenberg.

Parameter	Type	Default	Unit	Description
lon_geo_sp	real	14.119	deg	longitude coordinate of the special
			east	point
lat_geo_sp	real	52.205	deg	latitude coordinate of the special point
			north	
soiltype_sp	real	5.	-	soiltype of the special point
z0_sp	real	0.07	m	roughness lenght of the special point
rootdp_sp	real	0.6	m	rooting depth of the special point
plcovmn_sp	real	0.5	1	plant cover minimum of the special
				point
plcovmx_sp	real	0.9	1	plant cover maximum of the special
				point
laimn_sp	real	0.7	1	leaf area index minimum of the special
				point
laimx_sp	real	3.3	1	leaf area index maximum of the special
				point
for_d_sp	real		1	ground fraction covered by deciduous
				forest of the special point
for_e_sp	real		1	ground fraction covered by evergreen
				forest of the special point
fr_land_sp	real		1	fraction land cover of the special point

References

- [1] I. D. Stewart and T. R. Oke. Local climate zones for urban temperature studies. *Bulletin of the American Meteorological Society*, 93:1879–1900, 12 2012.
- [2] I. D. Stewart, T. R. Oke, and E. S. Krayenhoff. Evaluation of the 'local climate zone' scheme using temperature observations and model simulations. *International Journal of Climatology*, 34:1062–1080, 3 2014.
- [3] M. Varentsov, T. Samsonov, and M. Demuzere. Impact of urban canopy parameters on a megacity's modelled thermal environment. *Atmosphere*, 11, 12 2020.
- [4] H. Wouters, M. Demuzere, U. Blahak, K. Fortuniak, B. Maiheu, J. Camps, D. Tielemans, and N. P. V. Lipzig. The efficient urban canopy dependency parametrization (sury) v1.0 for atmospheric modelling: Description and application with the cosmo-clm model for a belgian summer. *Geoscientific Model Development*, 9:3027–3054, 2016.